

#### Binairy format:

# <SOF-SID10...SID0-RTR-IDE-r0-DLC3...0-DATABYTE1...DATABYTEn-CRC15...CRC1-CRCDEL-ACK-ACKDEL-EOF7...EOF1-IFS3...IFS1>

bits	Description	
SOF	Start Of Frame (always 0)	
SID10 & SID9	Priority (00: highest 11: lowest priority)	
SID8SID1	Address	
SID0	Always 0	
RTR	Remote Transmit Request	
IDE	Identifier Extension (always 0)	
r0	reserved (always 0)	
DLC3DLC0	Data Length Code (08)	
Databyte1	Command	
Databyte2	Parameter	
Databyte3	Parameter	
Databyte4	Parameter	
Databyte5	Parameter	
Databyte6	Parameter	
Databyte7	Parameter	
Databyte8	Parameter	
CRC15CRC1	Cyclic Redundancy Checksum	
CRCDEL	CRC Delimiter (always 1)	
ACK	Acknowledge slot (transmit 1 readback 0 if received correctly)	
ACKDEL	Acknowledge Delimiter (always 1)	
EOF7EOF1	End Of Frame (always 1111111)	
IFS3IFS1	InterFrame Space (always 111)	

#### The dimmer module can transmit the following commands:

- Updates LEDs on a push button module
- Clears LEDs on a push button module
- Sets LEDs on a push button module
- Blinks LEDs slowly on a push button module
- Blinks LEDs fast on a push button module
- Blinks LEDs very fast on a push button module

#### The dimmer module can transmit the following messages:

- Dimmer status
- Module type
- Local dim push button & dimmer switch status
- Dimmer slider status
- Bus error counter status
- First, second and third part of the dimmer name
- First, second and third part of the local dim push button name
- Memory data
- Memory data block (4 bytes)

#### The dimmer module can receive the following messages:

- Push button status
- Slider status

# The dimmer module can receive the following commands:

- Set dimmer value
- Set dimmer at last used dimvalue (Build 1006 or higher)
- Start dimmer timer
- Stop dimming (Build 1005 or higher)
- Dimmer status request
- Clear Push button Led
- Module type request
- Bus error counter status request

- Dimmer and/or local dim push button name request
- Read memory data
- Read memory data block (4 bytes)
- Memory dump request
- Write memory data
- Write memory data block (4 bytes)

# Transmits the local dim push button & dimmer switch status:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND PUSH BUTTON STATUS (H'00')

DATABYTE2 = Local dim push buttons just pressed / dimmer just switched on (1 = just pressed / switched on)

DATABYTE3 = Local dim push buttons just released / dimmer just switched off (1 = just released / switched off)

DATABYTE4 = Local dim push buttons long pressed (1 = longer than 0.85s pressed)

	Databyte2	Databyte3	Databyte4
Dimmer just switched on	B'000x0001'	B'000x0000'	B'000x0000'
Dimmer just switched off	B'000x0000'	B'000x0001'	B'000x0000'
Local Dim Push button just pressed	B'0001000x'	B'0000000x'	B'00000000'
Local Dim Push button just long pressed	B'0000000x'	B'0000000x'	B'00010000'
Local Dim Push button just released	B'0000000x'	B'0001000x'	B'00000000'

#### Transmits dimmer slider status:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND SLIDER STATUS (H'0F')

DATABYTE2 = Dimmer slider channel (H'01')

DATABYTE3 = Dimmer value 0...100% (slider status)

DATABYTE4 = H'00' (Slider channel not long pressed)

#### Transmit: Updates LEDs on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for updating the LEDs

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND\_UPDATE\_LED (H'F4')

DATABYTE2 = LED continuous on status (1 = LED on)

DATABYTE3 = LED slow blinking status (1 = LED slow blinking)

DATABYTE4 = LED fast blinking status (1 = LED fast blinking)

#### Remarks:

The continuous on bit overrides the blinking modes.

If the slow and fast blinking bits for a LED are both on, the LED blinks very fast.

#### Transmit: Clears LEDs on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for clearing LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND CLEAR LED (H'F5')

DATABYTE2 = LED bit numbers  $(1 = \overline{clear} LED)$ 

# Transmit: Sets LEDs on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for setting LEDs on

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND SET LED (H'F6')

DATABYTE2 = LED bit numbers ( $\overline{1}$  = set LED)

#### Transmit: Blinks LEDs slowly on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for slowly blinking LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND SLOW BLINKING LED (H'F7')

DATABYTE2 = LED bit numbers (1 = slow blink LED)

# Transmit: Blinks LEDs fast on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for fast blinking LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND FAST BLINKING LED (H'F8')

DATABYTE2 = LED bit numbers (1 = fast blink LED)

## Transmit: Blinks LEDs very fast on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for very fast blinking LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND\_VERYFAST\_BLINKING\_LED (H'F9')

DATABYTE2 = LED bit numbers (1 = very fast blink LED)

#### Transmits the dimmer status:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND DIMMER STATUS (H'EE')

DATABYTE2 = Mode setting

Contents	Mode	
0	Start/stop timer	
1	Staircase timer	
2	Dimmer	
3	Dimmer with memory	
4	Multi step dimmer	
5	Slow on dimmer	
6	Slow off dimmer	
7	Slow on/off dimmer	

DATABYTE3 = Dimvalue (0 to 100%)

DATABYTE4 = Led status

Contents	Mode	
B'00000000'	LED off	
B'10000000'	LED on	
B'01000000'	LED slow blinking	
B'00100000'	LED fast blinking	
B'00010000'	LED very fast blinking	

DATABYTE5 = high byte of current delay time

DATABYTE6 = mid byte of current delay time

DATABYTE7 = low byte of current delay time

DATABYTE8 = dimmer configuration

Contents	Contents	
B'1xxxx000'	Last 3 bits = version number	

Remark: [DATABYTE5][DATABYTE6][DATABYTE7] contain a 24-bit time in seconds

#### Transmits the module type:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 7 databytes to send

DATABYTE1 = COMMAND\_MODULE\_TYPE (H'FF')

DATABYTE2 = PWM\_LED\_STRIP\_DIMMER\_MODULE (H'0F')

DATABYTE3 = Mode setting

Contents	Mode	
0	Start/stop timer	
1	Staircase timer	
2	Dimmer	
3	Dimmer with memory	
4	Multi step dimmer	
5	Slow on dimmer	
6	Slow off dimmer	
7	Slow on/off dimmer	

# DATABYTE4 = Time switch setting

Contents	Time	
0	Momentary	
1	5s	
2	10s	
3	15s	
4	30s	
5	1min	
6	2min	
7	5min	
8	10min	
9	15min	
A	30min	
В	1h	
C	2h	
D	5h	
Е	1day	
F	No timer or max dimspeed	

# DATABYTE5 = dimmer configuration

Contents	Contents	
B'1xxxx000'	Last 3 bits = version number	

DATABYTE6 = Build Year

DATABYTE7 = Build Week

# Transmit: Bus error counter status

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND\_BUSERROR\_COUNTER\_STATUS (H'DA')

DATABYTE2 = Transmit error counter

DATABYTE3 = Receive error counter

DATABYTE4 = Bus off counter

```
Transmits the first part of the dimmer name:
```

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND\_DIMMER\_NAME\_PART1 (H'F0')

DATABYTE2 = Dimmer bit number (B' $0\overline{0}0000001\overline{}$ )

DATABYTE3 = Character 1 of the dimmer name

DATABYTE4 = Character 2 of the dimmer name

DATABYTE5 = Character 3 of the dimmer name

DATABYTE6 = Character 4 of the dimmer name

DATABYTE7 = Character 5 of the dimmer name

DATABYTE8 = Character 6 of the dimmer name

#### Transmits the second part of the dimmer name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND DIMMER NAME PART2 (H'F1')

DATABYTE2 = Dimmer bit number (B'00000001')

DATABYTE3 = Character 7 of the dimmer name

DATABYTE4 = Character 8 of the dimmer name

DATABYTE5 = Character 9 of the dimmer name

DATABYTE6 = Character 10 of the dimmer name

DATABYTE7 = Character 11 of the dimmer name

DATABYTE8 = Character 12 of the dimmer name

# Transmits the third part of the dimmer name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 6 databytes to send

DATABYTE1 = COMMAND DIMMER NAME PART3 (H'F2')

DATABYTE2 = Dimmer bit number (B'00000001')

DATABYTE3 = Character 13 of the dimmer name

DATABYTE4 = Character 14 of the dimmer name

DATABYTE5 = Character 15 of the dimmer name

DATABYTE6 = Character 16 of the dimmer name

#### Remarks:

Unused characters contain H'FF'.

#### Transmits the first part of the local dim push button name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND\_PUSH\_BUTTON\_NAME\_PART1 (H'F0')

DATABYTE2 = Push button identifier bit (B'00010000')

DATABYTE3 = Character 1 of the local dim push button name

DATABYTE4 = Character 2 of the local dim push button name

DATABYTE5 = Character 3 of the local dim push button name

DATABYTE6 = Character 4 of the local dim push button name

DATABYTE7 = Character 5 of the local dim push button name

DATABYTE8 = Character 6 of the local dim push button name

#### Transmits the second part of the local dim push button name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND PUSH BUTTON NAME PART2 (H'F1')

DATABYTE2 = Push button identifier bit (B'00010000')

DATABYTE3 = Character 7 of the local dim push button name

DATABYTE4 = Character 8 of the local dim push button name

DATABYTE5 = Character 9 of the local dim push button name

DATABYTE6 = Character 10 of the local dim push button name

DATABYTE7 = Character 11 of the local dim push button name

DATABYTE8 = Character 12 of the local dim push button name

#### Transmits the third part of the local dim push button name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 6 databytes to send

DATABYTE1 = COMMAND\_PUSH\_BUTTON\_NAME\_PART3 (H'F2')

DATABYTE2 = Push button identifier bit (B'00010000')

DATABYTE3 = Character 13 of the local dim push button name

DATABYTE4 = Character 14 of the local dim push button name

DATABYTE5 = Character 15 of the local dim push button name

DATABYTE6 = Character 16 of the local dim push button name

Remarks: Unused characters contain H'FF'.

# Transmits the memory data:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND MEMORY DATA (H'FE')

DATABYTE2 = High memory address (must be H'00')

DATABYTE3 = LOW memory address (H'00'...H'FF')

DATABYTE4 = memory data

### Transmits memory data block (4 bytes):

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND MEMORY DATA BLOCK (H'CC')

DATABYTE2 = High start address of memory block (must be H'00')

DATABYTE3 = LOW start address of memory block (H'00'...H'FC')

DATABYTE4 = memory data1

DATABYTE5 = memory data2

DATABYTE6 = memory data3

DATABYTE7 = memory data4

```
'Push button status' received:
```

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the push button module

RTR = 0

DLC3...DLC0 = 4 databytes received

DATABYTE1 = COMMAND PUSH BUTTON STATUS (H'00')

DATABYTE2 = Push buttons  $\overline{j}$ ust pressed (1 = just pressed)

DATABYTE3 = Push buttons just released (1 = just released)

DATABYTE4 = Push buttons long pressed (1 = longer than 0.85s pressed)

#### 'Slider status' received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the slider module

RTR = 0

DLC3...DLC0 = 4 databytes received

DATABYTE1 = COMMAND SLIDER STATUS (H'0F')

DATABYTE2 = Slider channel

DATABYTE3 = Slider status (0...100%)

DATABYTE4 = Slider channel long pressed (1 = longer than 0.85s pressed)

#### 'Clear LED' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND CLEAR LED (H'F5')

DATABYTE2 = LEDs to clear (a one clears the corresponding LED)

#### 'Set dimvalue' command received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND SET DIMVALUE (H'07')

DATABYTE2 = Dimmer bit number (B'00000001')

DATABYTE3 = Dimvalue (0 to 100%)

DATABYTE4 = high byte of dimspeed

DATABYTE5 = low byte of dimspeed

**Remark:** [DATABYTE4][DATABYTE5] contains a 16-bit time in seconds needed for dimming from 0 to 100%. If the dimspeed parameter contains zero then the dimspeed set by the hex switches on the dimmer module is chosen. If the dimspeed parameter contains H'FFFF' then the fastest dimspeed (1.5s) is chosen.

#### 'Set dimvalue at last used dimvalue' command received (Build 1006 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND\_RESTORE\_LAST\_DIMVALUE (H'11')

DATABYTE2 = Dimmer bit number (B'000000001')

DATABYTE3 = Don't care

DATABYTE4 = high byte of dimspeed

DATABYTE5 = low byte of dimspeed

**Remark:** [DATABYTE4][DATABYTE5] contains a 16-bit time in seconds needed for dimming from 0 to 100%. If the dimspeed parameter contains zero then the dimspeed set by the hex switches on the dimmer module is chosen. If the dimspeed parameter contains H'FFFF' then the fastest dimspeed (1.5s) is chosen.

### 'Stop dimming' command received (build 1005 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND STOP DIMMING (H'10')

DATABYTE2 = Dimmer bit number (B'00000001')

```
'Start dimmer timer' command received:
   SID10-SID9 = 00 (highest priority)
   SID8...SID1 = Address set by hex switches
   RTR = 0
   DLC3...DLC0 = 5 databytes received
   DATABYTE1 = COMMAND START DIMMER TIMER (H'08')
   DATABYTE2 = Dimmer bit number (B'00000001')
   DATABYTE3 = high byte of time-out time
   DATABYTE4 = mid byte of time-out time
   DATABYTE5 = low byte of time-out time
   Remark: [DATABYTE3][DATABYTE4][DATABYTE5] contains a 24-bit time-out time in seconds.
   If the time-out parameter contains zero then the timer starts for a time set by the hex switches on the dimmer module.
   If the time-out parameter contains H'FFxxxx' then the light switches permanently on (no time-out).
'Dimmer status request' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Address set by hex switches
   RTR = 0
   DLC3...DLC0 = 2 databytes received
   DATABYTE1 = COMMAND DIMMER STATUS REQUEST (H'FA')
   DATABYTE2 = Dimmer bit number (B'00000001')
'Module type request' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Address set by hex switches
   DLC3...DLC0 = 0 databytes received
'Bus error counter status request' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Address set by hex switches
   RTR = 0
   DLC3...DLC0 = 1 databytes to send
   DATABYTE1 = COMMAND BUS ERROR CONTER STATUS REQUEST (H'D9')
'Dimmer and/or dim push button name request' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Address set by hex switches
   RTR = 0
   DLC3...DLC0 = 2 databytes received
   DATABYTE1 = COMMAND DIMMER NAME REQUEST (H'EF')
   DATABYTE2 = Dimmer and/or dim push button bit number (B'00000001': dimmer identifier)
                                                          (B'00010000': dim push button identifier)
'Read data from memory' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Address set by hex switches
   RTR = 0
   DLC3...DLC0 = 3 databytes received
   DATABYTE1 = COMMAND READ DATA FROM MEMORY (H'FD')
   DATABYTE2 = High memory address (must be H'00')
   DATABYTE3 = LOW memory address (H'00'...H'FF')
'Memory dump request' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Address of the module
   RTR = 0
   DLC3...DLC0 = 1 databytes received
```

DATABYTE1 = COMMAND MEMORY DUMP REQUEST (H'CB')

#### 'Read data block from memory' command received:

```
SID10-SID9 = 11 (lowest priority)
```

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 3 databytes received

DATABYTE1 = COMMAND\_READ\_MEMORY\_BLOCK (H'C9')

DATABYTE2 = High memory address (must be H'00')

DATABYTE3 = LOW memory address (H'00'...H'FC')

#### 'Write data to memory' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 4 databytes received

DATABYTE1 = COMMAND WRITE DATA TO MEMORY (H'FC')

DATABYTE2 = High memory address (must be H'00')

DATABYTE3 = LOW memory address (H'00'...H'FF')

DATABYTE4 = memory data to write

Remark: Wait at least 10ms for sending a next command on the velbus.

# 'Write memory block' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address set by hex switches

RTR = 0

DLC3...DLC0 = 7 databytes received

DATABYTE1 = COMMAND WRITE MEMORY BLOCK (H'CA')

DATABYTE2 = High memory address (must be H'00')

DATABYTE3 = LOW memory address (H'00'...H'FC')

DATABYTE4 = memory databyte1 to write

DATABYTE5 = memory databyte2 to write

DATABYTE6 = memory databyte3 to write

DATABYTE7 = memory databyte4 to write

Remark: Wait for 'memory data block' feedback before sending a next command on the velbus.

# Memory map build 0947 or 1005:

Address	Contents	Address	Contents
H'0000'	Push button module address	H'0001'	Clear push button 1 bit numbers
H'0016'	Push button module address	H'0017'	Clear push button 12 bit numbers
H'0018'	Push button module address	H'0019'	Set push button 1 bit numbers
H'002E'	Push button module address	H'002F'	Set push button 12 bit numbers
H'0030'	Push button module address	H'0031'	Toggle push button 1 bit numbers
H'0046'	Push button module address	H'0047'	Toggle push button 12 bit numbers
H'0048'	Push button module address	H'0049'	Dim push button 1 bit numbers
•••			
H'005E'	Push button module address	H'005F'	Dim push button 12 bit numbers
H'0060'	Slider module address	H'0061'	Slider 1 bit numbers
•••			
H'0076'	Slider module address	H'0077'	Slider 12 bit numbers
H'0078'	Push button module address	H'0079	Dim up push button 1 bit numbers
•••			
H'008E'	Push button module address	H'008F'	Dim up push button 12 bit numbers
H'0090'	Push button module address	H'0091'	Dim down push button 1 bit numbers
H'00A6'	Push button module address	H'00A7'	Dim down push button 12 bit numbers
H'00A8'	Push button module address	H'00A9'	Atmospheric push button 1 bit numbers
•••			
H'00BE'	Push button module address	H'00DF'	Atmospheric push button 12 bit numbers
H'00C0'	Atmospheric dimvalue 1	H'00C1'	Atmospheric dimvalue 2
•••			
H'00CA'	Atmospheric dimvalue 11	H'00CB'	Atmospheric dimvalue 12
H'00CC'	Atmospheric dimtime 1	H'00CD'	Atmospheric dimtime 2
H'00D6'	Atmospheric dimtime 11	H'00D7'	Atmospheric dimtime 12
H'00D8'	Unused	H'00D9'	Unused
H'00DA'	Unused	H'00DB'	Unused
H'00DC'	Unused	H'00DD'	Unused
H'00DE'	Unused	H'00DF'	Unused
H'00E0'	Local Dim push button name character 1	H'00E1'	Local Dim push button name character 2
H'00EE'	Local Dim push button name character 15	H'00EF'	Local Dim push button name character 16
H'00F0'	Dimmer name character 1	H'00F1'	Dimmer name character 2
H'00FE'	Dimmer name character 15	H'00FF'	Dimmer name character 16

**Remark:** Unused locations contain H'FF'
Atmospheric dimyalue: 0 100%

Atmospheric dimvalue: 0...100%Atmospheric dimtime: bit 7 = 0  $\rightarrow$  time in seconds / bit 7 = 1  $\rightarrow$  time in minutes

Contents	Mode
B'00000000'	Fastest dimtime
B'00000001'	1 second
B'00000010'	2 seconds
B'01111110'	126 seconds
B'01111111'	Fastest dimtime
B'10000000'	Fastest dimtime
B'10000001'	1 minute
B'10000010'	2 minutes
B'11111110'	126 minutes
B'11111111'	Fastest dimtime