

Binairy format:

<SOF-SID10...SID0-RTR-IDE-r0-DLC3...0-DATABYTE1...DATABYTEn-CRC15...CRC1-CRCDEL-ACK-ACKDEL-EOF7...EOF1-IFS3...IFS1>

bits	Description
SOF	Start Of Frame (always 0)
SID10 & SID9	Priority (00: highest 11: lowest priority)
SID8SID1	Address
SID0	Always 0
RTR	Remote Transmit Request
IDE	Identifier Extension (always 0)
r0	reserved (always 0)
DLC3DLC0	Data Length Code (08)
Databyte1	Command
Databyte2	Parameter
Databyte3	Parameter
Databyte4	Parameter
Databyte5	Parameter
Databyte6	Parameter
Databyte7	Parameter
Databyte8	Parameter
CRC15CRC1	Cyclic Redundancy Checksum
CRCDEL	CRC Delimiter (always 1)
ACK	Acknowledge slot (transmit 1 readback 0 if received correctly)
ACKDEL	Acknowledge Delimiter (always 1)
EOF7EOF1	End Of Frame (always 1111111)
IFS3IFS1	InterFrame Space (always 111)

The dimmer module can transmit the following commands:

- Clears LEDs on a push button module
- Sets LEDs on a push button module
- Blinks LEDs slowly on a push button module
- Blinks LEDs fast on a push button module

The dimmer module can transmit the following messages:

- Dimmer channel status
- Module type
- Dimmer channel switch status
- Dimmer channel slider status
- Bus error counter status
- First, second and third part of the dimmer channel name
- Memory data
- Memory data block (4 bytes)

The dimmer module can receive the following messages:

- Push button status
- Slider status

The dimmer module can receive the following commands:

- Set dimmer channel value
- Set dimmer channel at last used dimvalue
- Start dimmer channel timer
- Stop channel dimming
- Forced off dimmer (Build 1105 or higher)
- Cancel forced off dimmer (Build 1105 or higher)
- Forced on dimmer (Build 1105 or higher)
- Cancel forced on dimmer (Build 1105 or higher)
- Inhibit dimmer (Build 1105 or higher)
- Cancel inhibit dimmer (Build 1105 or higher)
- Dimmer channel status request

- Clear Push button Led
- Module type request
- Bus error counter status request
- Dimmer channel name request
- Read memory data
- Read memory data block (4 bytes)
- Memory dump request
- Write memory data
- Write memory data block (4 bytes)

Transmits the dimmer channel switch status:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND_PUSH_BUTTON_STATUS (H'00')

DATABYTE2 = Dimmer channel just switched on (1 = just pressed / switched on)

DATABYTE3 = Dimmer channel just switched off (1 = just released / switched off)

DATABYTE4 = 0

	Databyte2	Databyte3	Databyte4
Dimmer ch1 just switched on	B'0000xxx1'	B'0000xxx0'	B'00000000'
Dimmer ch1 just switched off	B'0000xxx0'	B'0000xxx1'	B'00000000'
Dimmer ch2 just switched on	B'0000xx1x'	B'0000xx0x'	B'00000000'
Dimmer ch2 just switched off	B'0000xx0x'	B'0000xx1x'	B'00000000'
Dimmer ch3 just switched on	B'0000x1xx'	B'0000x0xx'	B'00000000'
Dimmer ch3 just switched off	B'0000x0xx'	B'0000x1xx'	B'00000000'
Dimmer ch4 just switched on	B'00001xxx'	B'00000xxx'	B'00000000'
Dimmer ch4 just switched off	B'00000xxx'	B'00001xxx'	B'00000000'

Transmits dimmer channel slider status:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND SLIDER STATUS (H'0F')

DATABYTE2 = Dimmer slider channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = Dimmer value 0...100% (slider status)

DATABYTE4 = H'00'

Transmit: Clears LEDs on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for clearing LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND CLEAR LED (H'F5')

DATABYTE2 = LED bit numbers (1 = clear LED)

Transmit: Sets LEDs on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for setting LEDs on

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND SET LED (H'F6')

DATABYTE2 = LED bit numbers ($\overline{1}$ = set LED)

Transmit: Blinks LEDs slowly on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for slowly blinking LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND_SLOW_BLINKING_LED (H'F7')

DATABYTE2 = LED bit numbers (1 = slow blink LED)

Transmit: Blinks LEDs fast on a push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module for fast blinking LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND_FAST_BLINKING_LED (H'F8')

DATABYTE2 = LED bit numbers (1 = fast blink LED)

Transmits the dimmer channel status:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND_DIMMERCONTROLLER_STATUS (H'B8')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = Disable/inhibit/Forced on setting

Contents	Setting
B'xxxxxx00'	Channel normal
B'xxxxxx01'	Channel inhibited
B'xxxxxx10'	Channel forced on
B'xxxxxx11'	Channel disabled

DATABYTE4 = Dimvalue (0 to 100%)

DATABYTE5 = Led status

Contents	Mode
B'00000000'	LED off
B'10000000'	LED on
B'01000000'	LED slow blinking
B'00100000'	LED fast blinking
B'00010000'	LED very fast blinking

DATABYTE6 = high byte of current delay time DATABYTE7 = mid byte of current delay time

DATABYTE8 = low byte of current delay time

Remark: [DATABYTE5][DATABYTE6][DATABYTE7] contain a 24-bit time in seconds

Transmits the module type:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 7 databytes to send

DATABYTE1 = COMMAND_MODULE_TYPE (H'FF')

DATABYTE2 = VMB4DC type (H'12')

DATABYTE3 = High byte of serial number

DATABYTE4 = Low byte of serial number

DATABYTE5 = Memorymap version

DATABYTE6 = Build year

DATABYTE7 = Build week

Transmit: Bus error counter status

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND_BUSERROR_COUNTER_STATUS (H'DA')

DATABYTE2 = Transmit error counter

DATABYTE3 = Receive error counter

DATABYTE4 = Bus off counter

Transmits the first part of the dimmer channel name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND DIMMER NAME PART1 (H'F0')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = Character 1 of the dimmer name

DATABYTE4 = Character 2 of the dimmer name

DATABYTE5 = Character 3 of the dimmer name

DATABYTE6 = Character 4 of the dimmer name

DATABYTE7 = Character 5 of the dimmer name

DATABYTE8 = Character 6 of the dimmer name

Transmits the second part of the dimmer channel name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND_DIMMER_NAME_PART2 (H'F1')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = Character 7 of the dimmer name

DATABYTE4 = Character 8 of the dimmer name

DATABYTE5 = Character 9 of the dimmer name

DATABYTE6 = Character 10 of the dimmer name

DATABYTE7 = Character 11 of the dimmer name

DATABYTE8 = Character 12 of the dimmer name

Transmits the third part of the dimmer channel name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 6 databytes to send

DATABYTE1 = COMMAND DIMMER NAME PART3 (H'F2')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = Character 13 of the dimmer name

DATABYTE4 = Character 14 of the dimmer name

DATABYTE5 = Character 15 of the dimmer name

DATABYTE6 = Character 16 of the dimmer name

Remarks:

Unused characters contain H'FF'.

Transmits the memory data:

SID10-SID9 = 11 (lowest priority) SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND_MEMORY_DATA (H'FE')

DATABYTE2 = High memory address

High address	Memory bank
H'00'	For channel 1 data
H'01'	For channel 2 data
H'02'	For channel 3 data
H'03'	For channel 4 data

DATABYTE3 = LOW memory address (H'00'...H'FF')

DATABYTE4 = memory data

Transmits memory data block (4 bytes):

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND MEMORY DATA BLOCK (H'CC')

DATABYTE2 = High start address of memory block

DATABYTE3 = LOW start address of memory block

DATABYTE4 = memory data1

DATABYTE5 = memory data2

DATABYTE6 = memory data3

DATABYTE7 = memory data4

Remark: address range: H'0000' to H'03FC'

'Push button status' received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the push button module

RTR = 0

DLC3...DLC0 = 4 databytes received

DATABYTE1 = COMMAND PUSH BUTTON STATUS (H'00')

DATABYTE2 = Push buttons just pressed (1 = just pressed)

DATABYTE3 = Push buttons just released (1 = just released)

DATABYTE4 = Push buttons long pressed (1 = longer than 0.85s pressed)

'Slider status' received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the slider module

RTR = 0

DLC3...DLC0 = 4 databytes received

DATABYTE1 = COMMAND SLIDER STATUS (H'0F')

DATABYTE2 = Slider channel

DATABYTE3 = Slider status (0...100%)

DATABYTE4 = don't care

'Clear LED' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the push button module

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND CLEAR LED (H'F5')

DATABYTE2 = LEDs to clear (a one clears the corresponding LED)

'Set dim channel value' command received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND SET DIMVALUE (H'07')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = Dimvalue (0 to 100%)

DATABYTE4 = high byte of dimspeed

DATABYTE5 = low byte of dimspeed

Remark: [DATABYTE4][DATABYTE5] contains a 16-bit time in seconds needed for dimming to the desired value.

'Set dim channel value at last used dimvalue' command received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND RESTORE LAST DIMVALUE (H'11')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = Don't care

DATABYTE4 = high byte of dimspeed

DATABYTE5 = low byte of dimspeed

Remark: [DATABYTE4][DATABYTE5] contains a 16-bit time in seconds needed for dimming to the desired value...

'Stop channel dimming' command received (build 1005 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND_STOP_DIMMING (H'10')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

'Start dimmer channel timer' command received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND_START_DIMMER_TIMER (H'08')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = high byte of time-out time

DATABYTE4 = mid byte of time-out time

DATABYTE5 = low byte of time-out time

Remark: [DATABYTE3][DATABYTE4][DATABYTE5] contains a 24-bit time-out time in seconds.

If the time-out parameter contains zero then no timer starts.

If the time-out parameter contains H'FFFFFF' then the light switches permanently on (no time-out).

'Forced off' command received (Build 1105 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND FORCED OFF (H'12')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = high byte of delay time

DATABYTE4 = mid byte of delay time

DATABYTE5 = low byte of delay time

Remark:

[DATABYTE3][DATABYTE4][DATABYTE5] contain a 24-bit time in seconds

The command will be skipped when the time parameter contains zero.

When the time parameter contains H'FFFFFF' then the dimmer is permanently forced off.

'Cancel forced off' command received (Build 1105 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND_CANCEL_FORCED_OFF (H'13')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

'Forced on' command received (Build 1105 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND_FORCED_ON (H'14')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = high byte of delay time

DATABYTE4 = mid byte of delay time

DATABYTE5 = low byte of delay time

Remark:

[DATABYTE3][DATABYTE4][DATABYTE5] contain a 24-bit time in seconds

The command will be skipped when the time parameter contains zero or the channels are already forced off.

When the time parameter contains H'FFFFFF' then the dimmer is permanently forced on.

'Cancel forced on' command received (Build 1105 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND_CANCEL_FORCED_ON (H'15')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

'Inhibit' command received (Build 1105 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND_INHIBIT (H'16')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

DATABYTE3 = high byte of delay time

DATABYTE4 = mid byte of delay time

DATABYTE5 = low byte of delay time

Remark:

[DATABYTE3][DATABYTE4][DATABYTE5] contain a 24-bit time in seconds

The command will be skipped when the time parameter contains zero or the channels are already forced off/on.

When the time parameter contains H'FFFFFF' then the dimmer is permanently inhibited.

'Cancel inhibit' command received (Build 1105 or higher):

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND_CANCEL_INHIBIT (H'17')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

'Dimmer channel status request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND DIMMER STATUS REQUEST (H'FA')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

'Module type request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 1

DLC3...DLC0 = 0 databytes received

'Bus error counter status request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 1 databytes to send

DATABYTE1 = COMMAND BUS ERROR CONTER STATUS REQUEST (H'D9')

'Dimmer channel name request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND_DIMMER_NAME_REQUEST (H'EF')

DATABYTE2 = Dimmer channel

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4

'Read data from memory' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 3 databytes received

DATABYTE1 = COMMAND_READ_DATA_FROM_MEMORY (H'FD')

DATABYTE2 = High memory address

High address	Memory bank
H'00'	For channel 1 data
H'01'	For channel 2 data
H'02'	For channel 3 data
H'03'	For channel 4 data

DATABYTE3 = LOW memory address (H'00'...H'FF')

'Memory dump request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 1 databytes received

DATABYTE1 = COMMAND_MEMORY_DUMP_REQUEST (H'CB')

'Read data block from memory' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 3 databytes received

DATABYTE1 = COMMAND READ MEMORY BLOCK (H'C9')

DATABYTE2 = High memory address

DATABYTE3 = LOW memory address

Remark: address range: H'0000' to H'03FC'

'Write data to memory' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 4 databytes received

DATABYTE1 = COMMAND_WRITE_DATA_TO_MEMORY (H'FC')

DATABYTE2 = High memory address

High address	Memory bank
H'00'	For channel 1 data
H'01'	For channel 2 data
H'02'	For channel 3 data
H'03'	For channel 4 data

DATABYTE3 = LOW memory address (H'00'...H'FF')

DATABYTE4 = memory data to write

Remark: Wait at least 10ms for sending a next command on the velbus.

'Write memory block' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 7 databytes received

DATABYTE1 = COMMAND WRITE MEMORY BLOCK (H'CA')

DATABYTE2 = High memory address

DATABYTE3 = LOW memory address

DATABYTE4 = memory databyte1 to write

DATABYTE5 = memory databyte2 to write

DATABYTE6 = memory databyte3 to write

DATABYTE7 = memory databyte4 to write

Remark:

Wait for 'memory data block' feedback before sending a next command on the velbus.

Address range: H'0000' to H'03FC'

Memory map:

Address	Contents	Address	Contents
H'0000'	Push button 1 module address	H'0001'	Push button 1 bit number
H'0002'	Push button 1 action for channel 1	H'0003'	Push button 1 first time parameter
H'0004'	Push button 1 second time parameter	H'0005'	Push button 1 third time parameter
H'0006'	Push button 2 module address	H'0007'	Push button 2 bit number
H'0008'	Push button 2 action for channel 1	H'0009'	Push button 2 first time parameter
H'000A'	Push button 2 second time parameter	H'000B'	Push button 2 third time parameter
H'00D8'	Push button 37 module address	H'00D9'	Push button 37 bit number
H'00DA'	Push button 37 action for channel 1	H'00DB'	Push button 37 first time parameter
H'00DC'	Push button 37 second time parameter	H'00DD'	Push button 37 third time parameter
H'00DE'	Preset 1 (25%) dimvalue for channel 1	H'00DF'	Preset 2 (50%) dimvalue for channel 1
H'00E0'	Preset 3 (75%) dimvalue for channel 1	H'00E1'	Preset 4 (100%) dimvalue for channel 1
H'00E2'	Preset 5 (75%) dimvalue for channel 1	H'00E3'	Preset 6 (50%) dimvalue for channel 1
H'00E4'	Preset 7 (25%) dimvalue for channel 1	H'00E5'	Preset 8 (255) dimvalue for channel 1
H'00E6'	Preset 9 (255) dimvalue for channel 1	H'00E7'	Preset 10 (255) dimvalue for channel 1
H'00E8'	Preset 11 (255) dimvalue for channel 1	H'00E9'	Preset 12 (255) dimvalue for channel 1
H'00EA'	Preset 13 (255) dimvalue for channel 1	H'00EB'	Preset dimvalue terminator for channel 1
H'00EC'	Linear or logarithmic curve for channel 1	H'00ED'	0 to 10V or 1 to 10V setting for channel 1
H'00EE'	Dim start delay for channel 1	H'00EF'	Dim switch off delay for channel 1
H'00F0'	Dimmer channel 1 name character 1	H'00F1'	Dimmer channel 1 name character 2
H'00FE'	Dimmer channel 1name character 15	H'00FF'	Dimmer channel 1 name character 16

Address	Contents	Address	Contents
H'0100'	Push button 1 module address	H'0101'	Push button 1 bit number
H'0102'	Push button 1 action for channel 2	H'0103'	Push button 1 first time parameter
H'0104'	Push button 1 second time parameter	H'0105'	Push button 1 third time parameter
H'0106'	Push button 2 module address	H'0107'	Push button 2 bit number
H'0108'	Push button 2 action for channel 2	H'0109'	Push button 2 first time parameter
H'010A'	Push button 2 second time parameter	H'010B'	Push button 2 third time parameter
H'01D8'	Push button 37 module address	H'01D9'	Push button 37 bit number
H'01DA'	Push button 37 action for channel 2	H'01DB'	Push button 37 first time parameter
H'01DC'	Push button 37 second time parameter	H'01DD'	Push button 37 third time parameter
H'01DE'	Preset 1 (25%)dimvalue for channel 2	H'01DF'	Preset 2 (50%)dimvalue for channel 2
H'01E0'	Preset 3 (75%)dimvalue for channel 2	H'01E1'	Preset 4 (100%)dimvalue for channel 2
H'01E2'	Preset 5 (75%) dimvalue for channel 2	H'01E3'	Preset 6 (50%) dimvalue for channel 2
H'01E4'	Preset 7 (25%) dimvalue for channel 2	H'01E5'	Preset 8 (255) dimvalue for channel 2
H'01E6'	Preset 9 (255) dimvalue for channel 2	H'01E7'	Preset 10 (255) dimvalue for channel 2
H'01E8'	Preset 11 (255) dimvalue for channel 2	H'01E9'	Preset 12 (255) dimvalue for channel 2
H'01EA'	Preset 13 (255) dimvalue for channel 2	H'01EB'	Preset dimvalue terminator for channel 2
H'01EC'	Linear or logarithmic curve for channel 2	H'01ED'	0 to 10V or 1 to 10V setting for channel 2
H'01EE'	Dim start delay for channel 2	H'01EF'	Dim switch off delay for channel 2
H'01F0'	Dimmer channel 2 name character 1	H'01F1'	Dimmer channel 2 name character 2
H'01FE'	Dimmer channel 2 name character 15	H'01FF'	Dimmer channel 2 name character 16

Address	Contents	Address	Contents
H'0200'	Push button 1 module address	H'0201'	Push button 1 bit number
H'0202'	Push button 1 action for channel 3	H'0203'	Push button 1 first time parameter
H'0204'	Push button 1 second time parameter	H'0205'	Push button 1 third time parameter
H'0206'	Push button 2 module address	H'0207'	Push button 2 bit number
H'0208'	Push button 2 action for channel 3	H'0209'	Push button 2 first time parameter
H'020A'	Push button 2 second time parameter	H'020B'	Push button 2 third time parameter
H'02D8'	Push button 37 module address	H'02D9'	Push button 37 bit number
H'02DA'	Push button 37 action for channel 3	H'02DB'	Push button 37 first time parameter
H'02DC'	Push button 37 second time parameter	H'02DD'	Push button 37 third time parameter
H'02DE'	Preset 1 (25%) dimvalue for channel 3	H'02DF'	Preset 2 (50%) dimvalue for channel 3
H'02E0'	Preset 3 (75%) dimvalue for channel 3	H'02E1'	Preset 4 (100%) dimvalue for channel 3
H'02E2'	Preset 5 (75%) dimvalue for channel 3	H'02E3'	Preset 6 (50%) dimvalue for channel 3
H'02E4'	Preset 7 (25%) dimvalue for channel 3	H'02E5'	Preset 8 (255) dimvalue for channel 3
H'02E6'	Preset 9 (255) dimvalue for channel 3	H'02E7'	Preset 10 (255) dimvalue for channel 3
H'02E8'	Preset 11 (255) dimvalue for channel 3	H'02E9'	Preset 12 (255) dimvalue for channel 3
H'02EA'	Preset 13 (255) dimvalue for channel 3	H'02EB'	Preset dimvalue terminator for channel 3
H'02EC'	Linear or logarithmic curve for channel 3	H'02ED'	0 to 10V or 1 to 10V setting for channel 3
H'02EE'	Dim start delay for channel 3	H'02EF'	Dim switch off delay for channel 3
H'02F0'	Dimmer channel 3 name character 1	H'02F1'	Dimmer channel 3 name character 2
H'02FE'	Dimmer channel 3name character 15	H'02FF'	Dimmer channel 3 name character 16

Address	Contents	Address	Contents
H'0300'	Push button 1 module address	H'0301'	Push button 1 bit number
H'0302'	Push button 1 action for channel 4	H'0303'	Push button 1 first time parameter
H'0304'	Push button 1 second time parameter	H'0305'	Push button 1 third time parameter
H'0306'	Push button 2 module address	H'0307'	Push button 2 bit number
H'0308'	Push button 2 action for channel 4	H'0309'	Push button 2 first time parameter
H'030A'	Push button 2 second time parameter	H'030B'	Push button 2 third time parameter
H'03D8'	Push button 37 module address	H'03D9'	Push button 37 bit number
H'03DA'	Push button 37 action for channel 4	H'03DB'	Push button 37 first time parameter
H'03DC'	Push button 37 second time parameter	H'03DD'	Push button 37 third time parameter
H'03DE'	Preset 1 (25%) dimvalue for channel 4	H'03DF'	Preset 2 (50%) dimvalue for channel 4
H'03E0'	Preset 3 (75%) dimvalue for channel 4	H'03E1'	Preset 4 (100%) dimvalue for channel 4
H'03E2'	Preset 5 (75%) dimvalue for channel 4	H'03E3'	Preset 6 (50%) dimvalue for channel 4
H'03E4'	Preset 7 (25%) dimvalue for channel 4	H'03E5'	Preset 8 (255) dimvalue for channel 4
H'03E6'	Preset 9 (255) dimvalue for channel 4	H'03E7'	Preset 10 (255) dimvalue for channel 4
H'03E8'	Preset 11 (255) dimvalue for channel 4	H'03E9'	Preset 12 (255) dimvalue for channel 4
H'03EA'	Preset 13 (255) dimvalue for channel 4	H'03EB'	Preset dimvalue terminator for channel 4
H'03EC'	Linear or logarithmic curve for channel 4	H'03ED'	0 to 10V or 1 to 10V setting for channel 4
H'03EE'	Dim start delay for channel 4	H'03EF'	Dim switch off delay for channel 4
H'03F0'	Dimmer channel 4 name character 1	H'03F1'	Dimmer channel 4 name character 2
H'03FE'	Dimmer channel 4 name character 15	H'03FF'	Dimmer channel 4 name character 16

Remark: Unused locations contain H'FF'

Linear dim curve: H'FF' Logarithmic dim curve: H'00' 0 to 10V dimmer: 0

0 to 10V dimmer: 0 1 to 10V dimmer: 1

Preset dimvalues: 0...100% or 255 for end of preset table

Preset dimvalue terminator: H'FF'

Dim start delay (default 0s) & Dim switch off delay (default 0s)

Contents	Delay
0	0s
1	0.013s
2	0.026s
255	3.315s

Mode number	Action			
0	Momentary	-	-	-
1	Off	-	-	-
2	'Off' with timers disabled	-	-	-
3	'Off' with timers disabled at short press	-	-	-
4	'Off' with timers disabled at long press	-	-	-
5	Slow off	Dim down time	-	-
6	On	-	-	-
7	'On' with timers disabled	-	-	-
8	'On' with timers disabled at short press	-	-	-
9	'On' with timers disabled at long press	-	-	-
10	Slow on	Dim up time	-	-
11	Toggle	-	-	-
12	'Toggle' with timers disabled	-	-	-
13	'Toggle' with timers disabled at short press	-	-	-
14	'Toggle' with timers disabled at long press	-	-	-
15	Slow on/off	Dim up time	Dim down time	-
16	Start/stop timer	Timeout	-	-
17	Start/stop timer with slow on/off	Timeout	Dim up time	Dim down time
18	Restartable timer	Timeout	-	-
19	Restartable timer with slow on/off	Timeout	Dim up time	Dim down time
20	Non restartable timer	Timeout	-	-
21	Non restartable timer with slow on/off	Timeout	Dim up time	Dim down time
22	Slow on at press, slow off at release + timeout	Timeout	Dim up time	Dim down time
23	Dim up	Timeout	-	-
24	Dim up at long press, on at short press	Timeout	-	-
25	Dim up at long press, memory at short press	Timeout	-	-
26	Dim down	Timeout	-	-
27	Dim down at long press, off at short press	Timeout	-	-
28	Dim	Timeout	-	-
29	Dim at long press, on or off at short press	Timeout	-	-
30	Dim at long press, memory or off at short press	Timeout	-	-
31	Atmospheric dimvalue	Timeout	Dim time	Dim value
32	Slider dimmer	-	-	-
33	Multi step dimmer	Timeout	Dim time	-
34	Disable at closed switch	-	-	-
35	Disable at opened switch	-	-	-
36	Disable at pressing push button	Timeout	-	-
37	Toggle disable at pressing push button	Timeout	-	-
38	Cancel disable at pressing push button	-	-	-
39	Forced 'On' at closed switch	-	-	-
40	Forced 'On' at opened switch	-	-	-
41	Forced 'On' at pressing push button	Timeout	-	-
42	Toggle forced 'On' at pressing push button	Timeout	-	-
43	Cancel Forced 'On' at pressing push button	-	-	-
44	Inhibit at closed switch	-	-	-
45	Inhibit at opened switch	-	-	-
46	Inhibit at pressing push button	Timeout	-	-
47	Toggle inhibit at pressing push button	Timeout	-	-
48	Cancel inhibit at pressing push button	-	-	-

Time parameter	Time or dim time	
0	No timer or fastest dim time	
1	1s	
2	2s	
119	1min59s	
120	2min	
121	2min15s	
131	4min45s	
132	5min	
133	5min30s	
•••		
181	29min30s	
182	30min	
183	31min	
•••		
211	59min	
212	1h	
213	1h15min	
•••		
227	4h45min	
228	5h	
229	5h30min	
•••		
237	9h30min	
238	10h	
239	11h	
•••		
251	23h	
252	1d	
253	2d	
254	3d	
255	infinite	

The dim time is limited to one day

Memory map version 2 (Build 1434 or higher):

Address	Contents	Address	Contents
H'0000'	Push button 1 module address	H'0001'	Push button 1 bit number
H'0002'	Push button 1 action for channel 1	H'0003'	Push button 1 first time parameter
H'0004'	Push button 1 second time parameter	H'0005'	Push button 1 third time parameter
H'0006'	Push button 2 module address	H'0007'	Push button 2 bit number
H'0008'	Push button 2 action for channel 1	H'0009'	Push button 2 first time parameter
H'000A'	Push button 2 second time parameter	H'000B'	Push button 2 third time parameter
•••			
H'00BA'	Push button 32 module address	H'00BB'	Push button 32 bit number
H'00BC'	Push button 32 action for channel 1	H'00BD	Push button 32 first time parameter
H'00BE'	Push button 32 second time parameter	H'00BF'	Push button 32 third time parameter
H'00C0'	Preset 1 (25%) dimvalue for channel 1	H'00C1'	Preset 2 (50%) dimvalue for channel 1
H'00C2'	Preset 3 (75%) dimvalue for channel 1	H'00C3'	Preset 4 (100%) dimvalue for channel 1
H'00C4'	Preset 5 (75%) dimvalue for channel 1	H'00C5'	Preset 6 (50%) dimvalue for channel 1
H'00C6'	Preset 7 (25%) dimvalue for channel 1	H'00C7'	Preset 8 (255) dimvalue for channel 1
H'00C8'	Preset 9 (255) dimvalue for channel 1	H'00C9'	Preset 10 (255) dimvalue for channel 1
H'00CA'	Preset 11 (255) dimvalue for channel 1	H'00CB'	Preset 12 (255) dimvalue for channel 1
H'00CC'	Preset 13 (255) dimvalue for channel 1	H'00CD'	Preset dimvalue terminator for channel 1
H'00CE'	Linear or logarithmic curve for channel 1	H'00CF'	0 to 10V or 1 to 10V setting for channel 1
H'00D0'	Dim start delay for channel 1	H'00D1'	Dim switch off delay for channel 1
H'00D2'	Transmit slider command for channel 1	H'00D3'	Not used
H'00D4'	Not used	H'00D5'	Terminator
H'00D6'	Channel 1 location id low byte	H'00D7'	Channel 1 location id high byte
H'00D8'	Channel 1 group id low byte	H'00D9'	Channel 1 group id high byte
H'00DA'	Channel 1 circuit id low byte	H'00DB'	Channel 1 circuit id high byte
H'00DC'	Channel 1 load id low byte	H'00DD'	Channel 1 load id high byte
H'00DE'	Module location id low byte	H'00DF'	Module location id high byte
H'00E0'	Module name character 1	H'00E1'	Module name character 2
H'00EE'	Module name character 15	H'00EF'	Module name character 16
H'00F0'	Dimmer channel 1 name character 1	H'00F1'	Dimmer channel 1 name character 2
•••			
H'00FE'	Dimmer channel 1name character 15	H'00FF'	Dimmer channel 1 name character 16

Address	Contents	Address	Contents
H'0100'	Push button 1 module address	H'0101'	Push button 1 bit number
H'0102'	Push button 1 action for channel 2	H'0103'	Push button 1 first time parameter
H'0104'	Push button 1 second time parameter	H'0105'	Push button 1 third time parameter
H'0106'	Push button 2 module address	H'0107'	Push button 2 bit number
H'0108'	Push button 2 action for channel 2	H'0109'	Push button 2 first time parameter
H'010A'	Push button 2 second time parameter	H'010B'	Push button 2 third time parameter
H'01BA'	Push button 32 module address	H'01BB'	Push button 32 bit number
H'01BC'	Push button 32 action for channel 2	H'01BD	Push button 32 first time parameter
H'01BE'	Push button 32 second time parameter	H'01BF'	Push button 32 third time parameter
H'01C0'	Preset 1 (25%) dimvalue for channel 2	H'01C1'	Preset 2 (50%) dimvalue for channel 2
H'01C2'	Preset 3 (75%) dimvalue for channel 2	H'01C3'	Preset 4 (100%) dimvalue for channel 2
H'01C4'	Preset 5 (75%) dimvalue for channel 2	H'01C5'	Preset 6 (50%) dimvalue for channel 2
H'01C6'	Preset 7 (25%) dimvalue for channel 2	H'01C7'	Preset 8 (255) dimvalue for channel 2
H'01C8'	Preset 9 (255) dimvalue for channel 2	H'01C9'	Preset 10 (255) dimvalue for channel 2
H'01CA'	Preset 11 (255) dimvalue for channel 2	H'01CB'	Preset 12 (255) dimvalue for channel 2
H'01CC'	Preset 13 (255) dimvalue for channel 2	H'01CD'	Preset dimvalue terminator for channel 2
H'01CE'	Linear or logarithmic curve for channel 2	H'01CF'	0 to 10V or 1 to 10V setting for channel 2
H'01D0'	Dim start delay for channel 2	H'01D1'	Dim switch off delay for channel 2
H'01D2'	Transmit slider command for channel 2	H'01D3'	Not used
H'01D4'	Not used	H'01D5'	Not used
H'01D6'	Channel 2 location id low byte	H'01D7'	Channel 2 location id high byte
H'01D8'	Channel 2 group id low byte	H'01D9'	Channel 2 group id high byte
H'01DA'	Channel 2 circuit id low byte	H'01DB'	Channel 2 circuit id high byte
H'01DC'	Channel 2 load id low byte	H'01DD'	Channel 2 load id high byte
H'01DE'	Module group id low byte	H'01DF'	Module group id high byte
H'01E0'	Module name character 17	H'01E1'	Module name character 18
H'01EE'	Module name character 31	H'01EF'	Module name character 32
H'01F0'	Dimmer channel 2 name character 1	H'01F1'	Dimmer channel 2 name character 2
H'01FE'	Dimmer channel 2 name character 15	H'01FF'	Dimmer channel 2 name character 16

Address	Contents	Address	Contents
H'0200'	Push button 1 module address	H'0201'	Push button 1 bit number
H'0202'	Push button 1 action for channel 3	H'0203'	Push button 1 first time parameter
H'0204'	Push button 1 second time parameter	H'0205'	Push button 1 third time parameter
H'0206'	Push button 2 module address	H'0207'	Push button 2 bit number
H'0208'	Push button 2 action for channel 3	H'0209'	Push button 2 first time parameter
H'020A'	Push button 2 second time parameter	H'020B'	Push button 2 third time parameter
H'02BA'	Push button 32 module address	H'02BB'	Push button 32 bit number
H'02BC'	Push button 32 action for channel 3	H'02BD	Push button 32 first time parameter
H'02BE'	Push button 32 second time parameter	H'02BF'	Push button 32 third time parameter
H'02C0'	Preset 1 (25%) dimvalue for channel 3	H'02C1'	Preset 2 (50%) dimvalue for channel 3
H'02C2'	Preset 3 (75%) dimvalue for channel 3	H'02C3'	Preset 4 (100%) dimvalue for channel 3
H'02C4'	Preset 5 (75%) dimvalue for channel 3	H'02C5'	Preset 6 (50%) dimvalue for channel 3
H'02C6'	Preset 7 (25%) dimvalue for channel 3	H'02C7'	Preset 8 (255) dimvalue for channel 3
H'02C8'	Preset 9 (255) dimvalue for channel 3	H'02C9'	Preset 10 (255) dimvalue for channel 3
H'02CA'	Preset 11 (255) dimvalue for channel 3	H'02CB'	Preset 12 (255) dimvalue for channel 3
H'02CC'	Preset 13 (255) dimvalue for channel 3	H'02CD'	Preset dimvalue terminator for channel 3
H'02CE'	Linear or logarithmic curve for channel 3	H'02CF'	0 to 10V or 1 to 10V setting for channel 3
H'02D0'	Dim start delay for channel 3	H'02D1'	Dim switch off delay for channel 3
H'02D2'	Transmit slider command for channel 3	H'02D3'	Not used
H'02D4'	Not used	H'02D5'	Not used
H'02D6'	Channel 3 location id low byte	H'02D7'	Channel 3 location id high byte
H'02D8'	Channel 3 group id low byte	H'02D9'	Channel 3 group id high byte
H'02DA'	Channel 3 circuit id low byte	H'02DB'	Channel 3 circuit id high byte
H'02DC'	Channel 3 load id low byte	H'02DD'	Channel 3 load id high byte
H'02DE'	Module circuit id low byte	H'02DF'	Module circuit id high byte
H'02E0'	Module name character 33	H'02E1'	Module name character 34
H'02EE'	Module name character 47	H'02EF'	Module name character 48
H'02F0'	Dimmer channel 3 name character 1	H'02F1'	Dimmer channel 3 name character 2
H'02FE'	Dimmer channel 3name character 15	H'02FF'	Dimmer channel 3 name character 16

Address	Contents	Address	Contents
H'0300'	Push button 1 module address	H'0301'	Push button 1 bit number
H'0302'	Push button 1 action for channel 4	H'0303'	Push button 1 first time parameter
H'0304'	Push button 1 second time parameter	H'0305'	Push button 1 third time parameter
H'0306'	Push button 2 module address	H'0307'	Push button 2 bit number
H'0308'	Push button 2 action for channel 4	H'0309'	Push button 2 first time parameter
H'030A'	Push button 2 second time parameter	H'030B'	Push button 2 third time parameter
H'03BA'	Push button 32 module address	H'03BB'	Push button 32 bit number
H'03BC'	Push button 32 action for channel 4	H'03BD	Push button 32 first time parameter
H'03BE'	Push button 32 second time parameter	H'03BF'	Push button 32 third time parameter
H'03C0'	Preset 1 (25%) dimvalue for channel 4	H'03C1'	Preset 2 (50%) dimvalue for channel 4
H'03C2'	Preset 3 (75%) dimvalue for channel 4	H'03C3'	Preset 4 (100%) dimvalue for channel 4
H'03C4'	Preset 5 (75%) dimvalue for channel 4	H'03C5'	Preset 6 (50%) dimvalue for channel 4
H'03C6'	Preset 7 (25%) dimvalue for channel 4	H'03C7'	Preset 8 (255) dimvalue for channel 4
H'03C8'	Preset 9 (255) dimvalue for channel 4	H'03C9'	Preset 10 (255) dimvalue for channel 4
H'03CA'	Preset 11 (255) dimvalue for channel 4	H'03CB'	Preset 12 (255) dimvalue for channel 4
H'03CC'	Preset 13 (255) dimvalue for channel 4	H'03CD'	Preset dimvalue terminator for channel 4
H'03CE'	Linear or logarithmic curve for channel 4	H'03CF'	0 to 10V or 1 to 10V setting for channel 4
H'03D0'	Dim start delay for channel 4	H'03D1'	Dim switch off delay for channel 4
H'03D2'	Transmit slider command for channel 4	H'03D3'	Not used
H'03D4'	Not used	H'03D5'	Not used
H'03D6'	Channel 4 location id low byte	H'03D7'	Channel 4 location id high byte
H'03D8'	Channel 4 group id low byte	H'03D9'	Channel 4 group id high byte
H'03DA'	Channel 4 circuit id low byte	H'03DB'	Channel 4 circuit id high byte
H'03DC'	Channel 4 load id low byte	H'03DD'	Channel 4 load id high byte
H'03DE'	Module load id low byte	H'03DF'	Module load id high byte
H'03E0'	Module name character 49	H'03E1'	Module name character 50
H'03EE'	Module name character 63	H'03EF'	Module name character 64
H'03EE'	Dim start delay for channel 4	H'03EF'	Dim switch off delay for channel 4
H'03F0'	Dimmer channel 4 name character 1	H'03F1'	Dimmer channel 4 name character 2
•••			
H'03FE'	Dimmer channel 4 name character 15	H'03FF'	Dimmer channel 4 name character 16

Remark: Unused locations contain H'FF'

Linear dim curve: H'FF' Logarithmic dim curve: H'00'

0 to 10V dimmer: 0 1 to 10V dimmer: 1

Do not transmit slider dimvalue command: 0 Transmit slider dimvalue command: 1

Preset dimvalues: 0...100% or 255 for end of preset table

Preset dimvalue terminator: H'FF'

Dim start delay (default 0s) & Dim switch off delay (default 0s)

Contents	Delay
0	Os
1	0.013s
2	0.026s
255	3.315s

Mode number	Action			
0	Momentary	-	-	-
1	Off	-	-	-
2	'Off' with timers disabled	-	-	-
3	'Off' with timers disabled at short press	-	-	-
4	'Off' with timers disabled at long press	-	-	-
5	Slow off	Dim down time	-	-
6	On	-	-	-
7	'On' with timers disabled	-	-	-
8	'On' with timers disabled at short press	-	-	-
9	'On' with timers disabled at long press	-	-	-
10	Slow on	Dim up time	-	-
11	Toggle	-	-	-
12	'Toggle' with timers disabled	-	-	-
13	'Toggle' with timers disabled at short press	-	-	-
14	'Toggle' with timers disabled at long press	-	-	-
15	Slow on/off	Dim up time	Dim down time	-
16	Start/stop timer	Timeout	-	-
17	Start/stop timer with slow on/off	Timeout	Dim up time	Dim down time
18	Restartable timer	Timeout	-	-
19	Restartable timer with slow on/off	Timeout	Dim up time	Dim down time
20	Non restartable timer	Timeout	-	-
21	Non restartable timer with slow on/off	Timeout	Dim up time	Dim down time
22	Slow on at press, slow off at release + timeout	Timeout	Dim up time	Dim down time
23	Dim up	Timeout	-	-
24	Dim up at long press, on at short press	Timeout	-	-
25	Dim up at long press, memory at short press	Timeout	-	-
26	Dim down	Timeout	-	-
27	Dim down at long press, off at short press	Timeout	-	-
28	Dim	Timeout	-	-
29	Dim at long press, on or off at short press	Timeout	-	-
30	Dim at long press, memory or off at short press	Timeout	-	-
31	Atmospheric dimvalue	Timeout	Dim time	Dim value
32	Slider dimmer	-	-	-
33	Multi step dimmer	Timeout	Dim time	-
34	Disable at closed switch	-	-	-
35	Disable at opened switch	-	-	-
36	Disable at pressing push button	Timeout	-	-
37	Toggle disable at pressing push button	Timeout	-	-
38	Cancel disable at pressing push button	-	-	-
39	Forced 'On' at closed switch	-	-	-
40	Forced 'On' at opened switch	-	-	-
41	Forced 'On' at pressing push button	Timeout	-	-
42	Toggle forced 'On' at pressing push button	Timeout	-	-
43	Cancel Forced 'On' at pressing push button	-	-	-
44	Inhibit at closed switch	-	-	-
45	Inhibit at opened switch	-	-	-
46	Inhibit at pressing push button	Timeout	-	-
40			_	
47	Toggle inhibit at pressing push button	Timeout	-	-

Time parameter	Time or dim time
0	No timer or fastest dim time
1	1s
2	2s
119	1min59s
120	2min
121	2min15s
131	4min45s
132	5min
133	5min30s
181	29min30s
182	30min
183	31min
211	59min
212	1h
213	1h15min
•••	
227	4h45min
228	5h
229	5h30min
•••	
237	9h30min
238	10h
239	11h
251	23h
252	1d
253	2d
254	3d
255	infinite

The dim time is limited to one day

Memory map version 3 (Build 1509 or higher):

Address	Contents	Address	Contents
H'0000'	Push button 1 module address	H'0001'	Push button 1 bit number
H'0002'	Push button 1 action for channel 1	H'0003'	Push button 1 first time parameter
H'0004'	Push button 1 second time parameter	H'0005'	Push button 1 third time parameter
H'0006'	Push button 2 module address	H'0007'	Push button 2 bit number
H'0008'	Push button 2 action for channel 1	H'0009'	Push button 2 first time parameter
H'000A'	Push button 2 second time parameter	H'000B'	Push button 2 third time parameter
H'00BA'	Push button 32 module address	H'00BB'	Push button 32 bit number
H'00BC'	Push button 32 action for channel 1	H'00BD	Push button 32 first time parameter
H'00BE'	Push button 32 second time parameter	H'00BF'	Push button 32 third time parameter
H'00C0'	Preset 1 (25%) dimvalue for channel 1	H'00C1'	Preset 2 (50%) dimvalue for channel 1
H'00C2'	Preset 3 (75%) dimvalue for channel 1	H'00C3'	Preset 4 (100%) dimvalue for channel 1
H'00C4'	Preset 5 (75%) dimvalue for channel 1	H'00C5'	Preset 6 (50%) dimvalue for channel 1
H'00C6'	Preset 7 (25%) dimvalue for channel 1	H'00C7'	Preset 8 (255) dimvalue for channel 1
H'00C8'	Preset 9 (255) dimvalue for channel 1	H'00C9'	Preset 10 (255) dimvalue for channel 1
H'00CA'	Preset 11 (255) dimvalue for channel 1	H'00CB'	Preset 12 (255) dimvalue for channel 1
H'00CC'	Preset 13 (255) dimvalue for channel 1	H'00CD'	Preset dimvalue terminator for channel 1
H'00CE'	Linear or logarithmic curve for channel 1	H'00CF'	0 to 10V or 1 to 10V setting for channel 1
H'00D0'	Dim start delay for channel 1	H'00D1'	Dim switch off delay for channel 1
H'00D2'	Transmit slider command for channel 1	H'00D3'	Minumum control factor
H'00D4'	Not used	H'00D5'	Terminator
H'00D6'	Channel 1 location id low byte	H'00D7'	Channel 1 location id high byte
H'00D8'	Channel 1 group id low byte	H'00D9'	Channel 1 group id high byte
H'00DA'	Channel 1 circuit id low byte	H'00DB'	Channel 1 circuit id high byte
H'00DC'	Channel 1 load id low byte	H'00DD'	Channel 1 load id high byte
H'00DE'	Module location id low byte	H'00DF'	Module location id high byte
H'00E0'	Module name character 1	H'00E1'	Module name character 2
H'00EE'	Module name character 15	H'00EF'	Module name character 16
H'00F0'	Dimmer channel 1 name character 1	H'00F1'	Dimmer channel 1 name character 2
H'00FE'	Dimmer channel 1name character 15	H'00FF'	Dimmer channel 1 name character 16

Address	Contents	Address	Contents
H'0100'	Push button 1 module address	H'0101'	Push button 1 bit number
H'0102'	Push button 1 action for channel 2	H'0103'	Push button 1 first time parameter
H'0104'	Push button 1 second time parameter	H'0105'	Push button 1 third time parameter
H'0106'	Push button 2 module address	H'0107'	Push button 2 bit number
H'0108'	Push button 2 action for channel 2	H'0109'	Push button 2 first time parameter
H'010A'	Push button 2 second time parameter	H'010B'	Push button 2 third time parameter
H'01BA'	Push button 32 module address	H'01BB'	Push button 32 bit number
H'01BC'	Push button 32 action for channel 2	H'01BD	Push button 32 first time parameter
H'01BE'	Push button 32 second time parameter	H'01BF'	Push button 32 third time parameter
H'01C0'	Preset 1 (25%) dimvalue for channel 2	H'01C1'	Preset 2 (50%) dimvalue for channel 2
H'01C2'	Preset 3 (75%) dimvalue for channel 2	H'01C3'	Preset 4 (100%) dimvalue for channel 2
H'01C4'	Preset 5 (75%) dimvalue for channel 2	H'01C5'	Preset 6 (50%) dimvalue for channel 2
H'01C6'	Preset 7 (25%) dimvalue for channel 2	H'01C7'	Preset 8 (255) dimvalue for channel 2
H'01C8'	Preset 9 (255) dimvalue for channel 2	H'01C9'	Preset 10 (255) dimvalue for channel 2
H'01CA'	Preset 11 (255) dimvalue for channel 2	H'01CB'	Preset 12 (255) dimvalue for channel 2
H'01CC'	Preset 13 (255) dimvalue for channel 2	H'01CD'	Preset dimvalue terminator for channel 2
H'01CE'	Linear or logarithmic curve for channel 2	H'01CF'	0 to 10V or 1 to 10V setting for channel 2
H'01D0'	Dim start delay for channel 2	H'01D1'	Dim switch off delay for channel 2
H'01D2'	Transmit slider command for channel 2	H'01D3'	Minumum control factor
H'01D4'	Not used	H'01D5'	Not used
H'01D6'	Channel 2 location id low byte	H'01D7'	Channel 2 location id high byte
H'01D8'	Channel 2 group id low byte	H'01D9'	Channel 2 group id high byte
H'01DA'	Channel 2 circuit id low byte	H'01DB'	Channel 2 circuit id high byte
H'01DC'	Channel 2 load id low byte	H'01DD'	Channel 2 load id high byte
H'01DE'	Module group id low byte	H'01DF'	Module group id high byte
H'01E0'	Module name character 17	H'01E1'	Module name character 18
•••			
H'01EE'	Module name character 31	H'01EF'	Module name character 32
H'01F0'	Dimmer channel 2 name character 1	H'01F1'	Dimmer channel 2 name character 2
H'01FE'	Dimmer channel 2 name character 15	H'01FF'	Dimmer channel 2 name character 16

Address	Contents	Address	Contents
H'0200'	Push button 1 module address	H'0201'	Push button 1 bit number
H'0202'	Push button 1 action for channel 3	H'0203'	Push button 1 first time parameter
H'0204'	Push button 1 second time parameter	H'0205'	Push button 1 third time parameter
H'0206'	Push button 2 module address	H'0207'	Push button 2 bit number
H'0208'	Push button 2 action for channel 3	H'0209'	Push button 2 first time parameter
H'020A'	Push button 2 second time parameter	H'020B'	Push button 2 third time parameter
H'02BA'	Push button 32 module address	H'02BB'	Push button 32 bit number
H'02BC'	Push button 32 action for channel 3	H'02BD	Push button 32 first time parameter
H'02BE'	Push button 32 second time parameter	H'02BF'	Push button 32 third time parameter
H'02C0'	Preset 1 (25%) dimvalue for channel 3	H'02C1'	Preset 2 (50%) dimvalue for channel 3
H'02C2'	Preset 3 (75%) dimvalue for channel 3	H'02C3'	Preset 4 (100%) dimvalue for channel 3
H'02C4'	Preset 5 (75%) dimvalue for channel 3	H'02C5'	Preset 6 (50%) dimvalue for channel 3
H'02C6'	Preset 7 (25%) dimvalue for channel 3	H'02C7'	Preset 8 (255) dimvalue for channel 3
H'02C8'	Preset 9 (255) dimvalue for channel 3	H'02C9'	Preset 10 (255) dimvalue for channel 3
H'02CA'	Preset 11 (255) dimvalue for channel 3	H'02CB'	Preset 12 (255) dimvalue for channel 3
H'02CC'	Preset 13 (255) dimvalue for channel 3	H'02CD'	Preset dimvalue terminator for channel 3
H'02CE'	Linear or logarithmic curve for channel 3	H'02CF'	0 to 10V or 1 to 10V setting for channel 3
H'02D0'	Dim start delay for channel 3	H'02D1'	Dim switch off delay for channel 3
H'02D2'	Transmit slider command for channel 3	H'02D3'	Minumum control factor
H'02D4'	Not used	H'02D5'	Not used
H'02D6'	Channel 3 location id low byte	H'02D7'	Channel 3 location id high byte
H'02D8'	Channel 3 group id low byte	H'02D9'	Channel 3 group id high byte
H'02DA'	Channel 3 circuit id low byte	H'02DB'	Channel 3 circuit id high byte
H'02DC'	Channel 3 load id low byte	H'02DD'	Channel 3 load id high byte
H'02DE'	Module circuit id low byte	H'02DF'	Module circuit id high byte
H'02E0'	Module name character 33	H'02E1'	Module name character 34
H'02EE'	Module name character 47	H'02EF'	Module name character 48
H'02F0'	Dimmer channel 3 name character 1	H'02F1'	Dimmer channel 3 name character 2
H'02FE'	Dimmer channel 3name character 15	H'02FF'	Dimmer channel 3 name character 16

Address	Contents	Address	Contents
H'0300'	Push button 1 module address	H'0301'	Push button 1 bit number
H'0302'	Push button 1 action for channel 4	H'0303'	Push button 1 first time parameter
H'0304'	Push button 1 second time parameter	H'0305'	Push button 1 third time parameter
H'0306'	Push button 2 module address	H'0307'	Push button 2 bit number
H'0308'	Push button 2 action for channel 4	H'0309'	Push button 2 first time parameter
H'030A'	Push button 2 second time parameter	H'030B'	Push button 2 third time parameter
H'03BA'	Push button 32 module address	H'03BB'	Push button 32 bit number
H'03BC'	Push button 32 action for channel 4	H'03BD	Push button 32 first time parameter
H'03BE'	Push button 32 second time parameter	H'03BF'	Push button 32 third time parameter
H'03C0'	Preset 1 (25%) dimvalue for channel 4	H'03C1'	Preset 2 (50%) dimvalue for channel 4
H'03C2'	Preset 3 (75%) dimvalue for channel 4	H'03C3'	Preset 4 (100%) dimvalue for channel 4
H'03C4'	Preset 5 (75%) dimvalue for channel 4	H'03C5'	Preset 6 (50%) dimvalue for channel 4
H'03C6'	Preset 7 (25%) dimvalue for channel 4	H'03C7'	Preset 8 (255) dimvalue for channel 4
H'03C8'	Preset 9 (255) dimvalue for channel 4	H'03C9'	Preset 10 (255) dimvalue for channel 4
H'03CA'	Preset 11 (255) dimvalue for channel 4	H'03CB'	Preset 12 (255) dimvalue for channel 4
H'03CC'	Preset 13 (255) dimvalue for channel 4	H'03CD'	Preset dimvalue terminator for channel 4
H'03CE'	Linear or logarithmic curve for channel 4	H'03CF'	0 to 10V or 1 to 10V setting for channel 4
H'03D0'	Dim start delay for channel 4	H'03D1'	Dim switch off delay for channel 4
H'03D2'	Transmit slider command for channel 4	H'03D3'	Minumum control factor
H'03D4'	Not used	H'03D5'	Not used
H'03D6'	Channel 4 location id low byte	H'03D7'	Channel 4 location id high byte
H'03D8'	Channel 4 group id low byte	H'03D9'	Channel 4 group id high byte
H'03DA'	Channel 4 circuit id low byte	H'03DB'	Channel 4 circuit id high byte
H'03DC'	Channel 4 load id low byte	H'03DD'	Channel 4 load id high byte
H'03DE'	Module load id low byte	H'03DF'	Module load id high byte
H'03E0'	Module name character 49	H'03E1'	Module name character 50
H'03EE'	Module name character 63	H'03EF'	Module name character 64
H'03EE'	Dim start delay for channel 4	H'03EF'	Dim switch off delay for channel 4
H'03F0'	Dimmer channel 4 name character 1	H'03F1'	Dimmer channel 4 name character 2
•••			
H'03FE'	Dimmer channel 4 name character 15	H'03FF'	Dimmer channel 4 name character 16

Remark: Unused locations contain H'FF'

Linear dim curve: H'FF' Logarithmic dim curve: H'00'

0 to 10V dimmer: 0 1 to 10V dimmer: 1

Do not transmit slider dimvalue command: 0 Transmit slider dimvalue command: 1

Preset dimvalues: 0...100% or 255 for end of preset table

Preset dimvalue terminator: H'FF'

Dim start delay (default 0s) & Dim switch off delay (default 0s)

Contents	Delay
0	0s
1	0.013s
2	0.026s
255	3.315s

Minumum control factor = $255 - (\min\% * 255/100)$

Mode number	Action			
0	Momentary	-	-	-
1	Off	-	-	-
2	'Off' with timers disabled	-	_	_
3	'Off' with timers disabled at short press	-	-	_
4	'Off' with timers disabled at long press	-	_	_
5	Slow off	Dim down time	_	_
6	On	-	-	_
7	'On' with timers disabled	-	-	_
8	'On' with timers disabled at short press	-	-	-
9	'On' with timers disabled at long press	-	-	-
10	Slow on	Dim up time	-	-
11	Toggle	-	-	-
12	'Toggle' with timers disabled	-	-	_
13	'Toggle' with timers disabled at short press	-	-	-
14	'Toggle' with timers disabled at long press	-	_	_
15	Slow on/off	Dim up time	Dim down time	-
16	Start/stop timer	Timeout	-	_
17	Start/stop timer with slow on/off	Timeout	Dim up time	Dim down time
18	Restartable timer	Timeout	-	-
19	Restartable timer with slow on/off	Timeout	Dim up time	Dim down time
20	Non restartable timer	Timeout	-	-
21	Non restartable timer with slow on/off	Timeout	Dim up time	Dim down time
22	Slow on at press, slow off at release + timeout	Timeout	Dim up time	Dim down time
23	Dim up	Timeout	-	-
24	Dim up at long press, on at short press	Timeout	-	_
25	Dim up at long press, memory at short press	Timeout	-	-
26	Dim down	Timeout	-	_
27	Dim down at long press, off at short press	Timeout	-	_
28	Dim	Timeout	-	-
29	Dim at long press, on or off at short press	Timeout	-	_
30	Dim at long press, memory or off at short press	Timeout	-	-
31	Atmospheric dimvalue	Timeout	Dim time	Dim value
32	Slider dimmer	-	-	-
33	Multi step dimmer	Timeout	Dim time	-
34	Disable at closed switch	-	-	-
35	Disable at opened switch	-	-	-
36	Disable at pressing push button	Timeout	-	-
37	Toggle disable at pressing push button	Timeout	-	-
38	Cancel disable at pressing push button	-	-	-
39	Forced 'On' at closed switch	-	-	-
40	Forced 'On' at opened switch	-	-	-
41	Forced 'On' at pressing push button	Timeout	-	-
42	Toggle forced 'On' at pressing push button	Timeout	-	-
43	Cancel Forced 'On' at pressing push button	-	-	-
44	Inhibit at closed switch	-	-	-
45	Inhibit at opened switch	-	-	-
		†	1	1
46	Inhibit at pressing push button	Timeout	-	-
46 47	Inhibit at pressing push button Toggle inhibit at pressing push button	Timeout Timeout	-	-

Time parameter	Time or dim time
0	No timer or fastest dim time
1	1s
2	2s
119	1min59s
120	2min
121	2min15s
131	4min45s
132	5min
133	5min30s
•••	
181	29min30s
182	30min
183	31min
•••	
211	59min
212	1h
213	1h15min
•••	
227	4h45min
228	5h
229	5h30min
•••	
237	9h30min
238	10h
239	11h
251	23h
252	1d
253	2d
254	3d
255	infinite

The dim time is limited to one day