

Binairy format:

< SOF-SID10...SID0-RTR-IDE-r0-DLC3...0-DATABYTE1...DATABYTEn-CRC15...CRC1-CRCDEL-ACK-ACKDEL-EOF7...EOF1-IFS3...IFS1>

bits	Description
SOF	Start Of Frame (always 0)
SID10 & SID9	Priority (00: highest 11: lowest priority)
SID8SID1	Address
SID0	Always 0
RTR	Remote Transmit Request
IDE	Identifier Extension (always 0)
r0	reserved (always 0)
DLC3DLC0	Data Length Code (08)
Databyte1	Command
Databyte2	Parameter
Databyte3	Parameter
Databyte4	Parameter
Databyte5	Parameter
Databyte6	Parameter
Databyte7	Parameter
Databyte8	Parameter
CRC15CRC1	Cyclic Redundancy Checksum
CRCDEL	CRC Delimiter (always 1)
ACK	Acknowledge slot (transmit 1 readback 0 if received correctly)
ACKDEL	Acknowledge Delimiter (always 1)
EOF7EOF1	End Of Frame (always 1111111)
IFS3IFS1	InterFrame Space (always 111)

The module can transmit the following messages:

- Channel status
- Module status
- Module type
- Bus error counter status
- First, second and third part of the channel names
- Memory data
- Memory data block (4 bytes)
- Real-time clock status
- Date status
- Real-time clock status request
- Clear linked push button led
- Set linked push button led
- Slow blink linked push button led
- Fast blink linked push button led

The module can receive the following commands:

- Linked push button status
- Module type request
- Module status request
- Channel name request
- Clear channel led
- Set channel led
- Slow blink channel led
- Fast blink channel led
- Very fast channel led
- Update channel leds
- Read memory data
- Read memory data block (4 bytes)

- Memory dump request
- Write memory data
- Write memory data block (4 bytes) Bus error counter status request
- Real-time clock status request
- Set real-time clock
- Set date
- Set local alarm clock
- Set global alarm clock
- Lock channel
- Unlock channel
- Disable channel program
- Enable channel program
- Select program

Transmits real time clock status request:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = H'00'

RTR = 0

DLC3...DLC0 = 1 databyte to send

DATABYTE1 = COMMAND REALTIME CLOCK STATUS REQUEST (H'D7')

Transmits the real time clock status:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND REALTIME CLOCK STATUS (H'D8')

DATABYTE2 = Dav

Contents	Day
0	Monday
1	Tuesday
2	Wednesday
3	Thursday
4	Friday
5	Saturday
6	Sunday

DATABYTE3 = $\overline{\text{Hour}(0...23)}$

DATABYTE4 = Minute (0...59)

Transmits the date status:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 5 databytes to send

DATABYTE1 = COMMAND DATE STATUS (H'B7')

DATABYTE2 = Day(1...31)

DATABYTE3 = Month (1...12)

DATABYTE4 = High byte of Year

DATABYTE5 = Low byte of Year

Transmits the channel switch status:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND_PUSH_BUTTON_STATUS (H'00')

DATABYTE2 = Channel just pressed

DATABYTE3 = Channel just released

DATABYTE4 = Channel long pressed

Transmits the module type:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 7 databytes to send

DATABYTE1 = COMMAND MODULE TYPE (H'FF')

DATABYTE2 = VMB8PBU type (H'16')

DATABYTE3 = High byte of serial number

DATABYTE4 = Low byte of serial number

DATABYTE5 = Memorymap version

DATABYTE6 = Build year

DATABYTE7 = Build week

Transmits the module status:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 5 databytes to send

DATABYTE1 = COMMAND MODULE STATUS (H'ED')

DATABYTE2 = channel 1 to 8 status (1 = pressed / 0 = released)

DATABYTE3 = enabled/disable channel status (1 = enabled / 0 = disabled)

DATABYTE4 = normal/inverted channel status (1 = normal / 0 = inverted)

DATABYTE5 = locked channel status (0 = unlocked / 1 = locked)

DATABYTE6 = disabled channel program status (0 = program enabled / 1 = program disabled)

DATABYTE7 = alarm & program selection

Contents	Selected programl
B'xxxxxx00'	None
B'xxxxxx01'	Summer
B'xxxxxx10'	Winter
B'xxxxxx11'	Holiday
B'xxxxx0xx'	Alarm 1 off
B'xxxxx1xx'	Alarm 1 on
B'xxxx0xxx'	Local alarm 1
B'xxxx1xxx'	Global alarm 1
B'xxx0xxxx'	Alarm 2 off
B'xxx1xxxx'	Alarm 2 on
B'xx0xxxxx'	Local alarm 2
B'xx1xxxxx'	Global alarm 2
B'x0xxxxxx'	Sunrise disabled
B'x1xxxxxx'	Sunrise enabled
B'0xxxxxxx'	Sunset disabled
B'1xxxxxxx'	Sunset enabled

Transmit: Bus error counter status

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND BUSERROR COUNTER STATUS (H'DA')

DATABYTE2 = Transmit error counter

DATABYTE3 = Receive error counter

DATABYTE4 = Bus off counter

Transmits the memory data:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND MEMORY DATA (H'FE')

DATABYTE2 = High memory address

DATABYTE3 = LOW memory address

DATABYTE4 = memory data

Remark: address range: H'0000' to H'03FF'

Transmits memory data block (4 bytes):

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 7 databytes to send

DATABYTE1 = COMMAND MEMORY DATA BLOCK (H'CC')

DATABYTE2 = High start address of memory block

DATABYTE3 = LOW start address of memory block

DATABYTE4 = memory data1

DATABYTE5 = memory data2

DATABYTE6 = memory data3

DATABYTE7 = memory data4

Remark: address range: H'0000' to H'03FC'

Transmits the first part of channel name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND CHANNEL NAME PART1 (H'F0')

DATABYTE2 = channel bit

Contents	Channel
B'00000001'	channel 1
B'00000010'	channel 2
B'00000100'	channel 3
B'00001000'	channel 4
B'00010000'	channel 5
B'00100000'	channel 6
B'01000000'	channel 7
B'10000000'	channel 8

DATABYTE3 = Character 1 of the channel name

DATABYTE4 = Character 2 of the channel name

DATABYTE5 = Character 3 of the channel name

DATABYTE6 = Character 4 of the channel name

DATABYTE7 = Character 5 of the channel name

DATABYTE8 = Character 6 of the channel name

Transmits the second part of the channel name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 8 databytes to send

DATABYTE1 = COMMAND_CHANNEL_NAME_PART2 (H'F1')

DATABYTE2 = Channel bit

= 01101111101 010	
Contents	Channel
B'00000001'	channel 1
B'00000010'	channel 2
B'00000100'	channel 3
B'00001000'	channel 4
B'00010000'	channel 5
B'00100000'	channel 6
B'01000000'	channel 7
B'10000000'	channel 8

DATABYTE3 = Character 7 of the channel name

DATABYTE4 = Character 8 of the channel name

DATABYTE5 = Character 9 of the channel name

DATABYTE6 = Character 10 of the channel name

DATABYTE7 = Character 11 of the channel name DATABYTE8 = Character 12 of the channel name

Transmits the third part of the channel name:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 6 databytes to send

DATABYTE1 = COMMAND CHANNEL NAME PART3 (H'F2')

DATABYTE2 = channel bit

Contents	Channel
B'00000001'	channel 1
B'00000010'	channel 2
B'00000100'	channel 3
B'00001000'	channel 4
B'00010000'	channel 5
B'00100000'	channel 6
B'01000000'	channel 7
B'10000000'	channel 8

DATABYTE3 = Character 13 of the channel name

DATABYTE4 = Character 14 of the channel name

DATABYTE5 = Character 15 of the channel name

DATABYTE6 = Character 16 of the channel name

Remarks:

Unused characters contain H'FF'.

Transmit: Clears LEDs on a linked push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the linked push button module for clearing LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND CLEAR LED (H'F5')

DATABYTE2 = LED bit numbers (1 = clear LED)

Transmit: Sets LEDs on a linked push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the linked push button module for setting LEDs on

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND_SET_LED (H'F6')

DATABYTE2 = LED bit numbers (1 = set LED)

Transmit: Blinks LEDs slowly on a linked push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the linked push button module for slowly blinking LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND SLOW BLINKING LED (H'F7')

DATABYTE2 = LED bit numbers (1 = slow blink LED)

Transmit: Blinks LEDs fast on a linked push button module:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the linked push button module for fast blinking LEDs

RTR = 0

DLC3...DLC0 = 2 databytes to send

DATABYTE1 = COMMAND_FAST_BLINKING_LED (H'F8')

DATABYTE2 = LED bit numbers (1 = fast blink LED)

'Linked push button status' received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Address of the linked push button module

RTR = 0

DLC3...DLC0 = 4 databytes received

DATABYTE1 = COMMAND PUSH BUTTON STATUS (H'00')

DATABYTE2 = Linked push buttons just pressed (1 = just pressed)

DATABYTE3 = Linked push buttons just released (1 = just released)

DATABYTE4 = linked push buttons long pressed (1 = longer than 0.85s pressed)

'Real time clock status request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 1 databyte to send

DATABYTE1 = COMMAND REALTIME CLOCK STATUS REQUEST (H'D7')

'Set real time clock' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = H'00'

RTR = 0

DLC3...DLC0 = 4 databytes to send

DATABYTE1 = COMMAND SET REALTIME CLOCK (H'D8')

DATABYTE2 = Day of week

Contents day of week'	Description
H'00'	Monday
H'01'	Tuesday
H'02'	Wednesday
H'03'	Thursday
H'04'	Friday
H'05'	Saterday
H'06'	Sunday

DATABYTE3 = Hours (0...23)

DATABYTE4 = Minutes (0...59)

'Set date' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = H'00'

RTR = 0

DLC3...DLC0 = 5 databytes to send

DATABYTE1 = COMMAND SET REALTIME DATE (H'B7')

DATABYTE2 = Day (1...31)

DATABYTE3 = Month (1...12)

DATABYTE4 = High byte of Year

DATABYTE5 = Low byte of Year

'Set global clock alarm' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = H'00'

RTR = 0

DLC3...DLC0 = 7 databytes to send

DATABYTE1 = COMMAND SET ALARM CLOCK (H'C3')

DATABYTE2 = Alarm number (1 or 2)

DATABYTE3 = Wake up hour (0...23)

DATABYTE4 = Wake up minute (0...59)

DATABYTE5 = Go to bed hour (0...23)

DATABYTE6 = Go to bed minute (0...59)

DATABYTE7 = Clock alarm enable flag (0 = disabled / 1 = enabled)

'Set local clock alarm' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 7 databytes to send

DATABYTE1 = COMMAND_SET_ALARM_CLOCK (H'C3')

DATABYTE2 = Alarm number (1 or 2)

DATABYTE3 = Wake up hour (0...23)

DATABYTE4 = Wake up minute (0...59)

DATABYTE5 = Go to bed hour (0...23)

DATABYTE6 = Go to bed minute (0...59)

DATABYTE7 = Clock alarm enable flag (0 = disabled / 1 = enabled)

'Module type request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 1

DLC3...DLC0 = 0 databytes received

'Module status request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND_MODULE_STATUS_REQUEST (H'FA')

DATABYTE2 = don't care

'Channel name request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND CHANNEL NAME REQUEST (H'EF')

DATABYTE2 = channel bit

Contents	Channel
B'00000001'	channel 1
B'00000010'	channel 2
B'00000100'	channel 3
B'00001000'	channel 4
B'00010000'	channel 5
B'00100000'	channel 6
B'01000000'	channel 7
B'10000000'	channel 8

'Clear channel LED' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND CLEAR LED (H'F5')

DATABYTE2 = LEDs to clear (a one clears the corresponding LED of channel 1 to 8)

'Set channel LED' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND SET LED (H'F6')

DATABYTE2 = LEDs to set (a one sets the corresponding LED of channel 1 to 8)

```
'Slow blink channel LED' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Module address
   RTR = 0
   DLC3...DLC0 = 2 databytes received
   DATABYTE1 = COMMAND SLOW BLINK LED (H'F7')
   DATABYTE2 = LEDs to blink slow (a one blinks slow the corresponding LED of channel 1 to 8)
'Fast blink channel LED' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Module address
   RTR = 0
   DLC3...DLC0 = 2 databytes received
   DATABYTE1 = COMMAND FAST BLINK LED (H'F8')
   DATABYTE2 = LEDs to blink fast (a one blinks fast the corresponding LED of channel 1 to 8)
'Very fast blink channel LED' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Module address
   RTR = 0
   DLC3...DLC0 = 2 databytes received
   DATABYTE1 = COMMAND VERY FAST BLINK LED (H'F9')
   DATABYTE2 = LEDs to blink very fast (a one blinks very fast the corresponding LED of channel 1 to 8)
'Update channel LEDs' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Module address
   RTR = 0
   DLC3...DLC0 = 4 databytes received
   DATABYTE1 = COMMAND UPDATE LED STATUS (H'F4')
   DATABYTE2 = LEDs to set (a one sets the corresponding LED of channel 1 to 8)
   DATABYTE3 = LEDs to blink slow (a one blinks slow the corresponding LED of channel 1 to 8)
   DATABYTE4 = LEDs to blink fast (a one blinks very fast the corresponding LED of channel 1 to 8)
   The 'LEDs to set' status overrides the blinking modes.
   Very fast blinking if slow & fast blinking are set.
'Read data from memory' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Module address
   RTR = 0
   DLC3...DLC0 = 3 databytes received
   DATABYTE1 = COMMAND READ DATA FROM MEMORY (H'FD')
   DATABYTE2 = High memory address
   DATABYTE3 = LOW memory address
   Remark: address range: H'0000' to H'03FF'
'Memory dump request' command received:
   SID10-SID9 = 11 (lowest priority)
   SID8...SID1 = Module address
   RTR = 0
   DLC3...DLC0 = 1 databytes received
   DATABYTE1 = COMMAND MEMORY DUMP REQUEST (H'CB')
```

'Read data block from memory' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 3 databytes received

DATABYTE1 = COMMAND_READ_MEMORY_BLOCK (H'C9')

DATABYTE2 = High memory address

DATABYTE3 = LOW memory address

Remark: address range: H'0000' to H'03FC'

'Write data to memory' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 4 databytes received

DATABYTE1 = COMMAND_WRITE_DATA_TO_MEMORY (H'FC')

DATABYTE2 = High memory address

DATABYTE3 = LOW memory address (H'00'...H'FF')

DATABYTE4 = memory data to write

Remark

Wait at least 10ms for sending a next command on the velbus.

Address range: H'0000' to H'03FF'

'Write memory block' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Address of the module

RTR = 0

DLC3...DLC0 = 7 databytes received

DATABYTE1 = COMMAND WRITE MEMORY BLOCK (H'CA')

DATABYTE2 = High memory address

DATABYTE3 = LOW memory address

DATABYTE4 = memory databyte1 to write

DATABYTE5 = memory databyte2 to write

DATABYTE6 = memory databyte3 to write

DATABYTE7 = memory databyte4 to write

Remark:

Wait for 'memory data block' feedback before sending a next command on the velbus.

Address range: H'0000' to H'03FC'

'Bus error counter status request' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 1 databytes to send

DATABYTE1 = COMMAND BUS ERROR CONTER STATUS REQUEST (H'D9')

'Unlock channel' command received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND_CANCEL_FORCED_OFF (H'13')

DATABYTE2 = Channel bit

Contents	Channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'10000000'	Channel 8

'Lock channel' command received:

SID10-SID9 = 00 (highest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND FORCED OFF (H'12')

DATABYTE2 = Channel bit

Contents	Dimmer channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'10000000'	Channel 8

DATABYTE3 = high byte of delay time

DATABYTE4 = mid byte of delay time

DATABYTE5 = low byte of delay time

Remark

[DATABYTE3][DATABYTE4][DATABYTE5] contain a 24-bit time in seconds

The command will be skipped when the time parameter contains zero.

When the time parameter contains H'FFFFFF' then the channelwill be permanently locked.

'Enable Channel Program' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received

DATABYTE1 = COMMAND_ENABLE PROGRAM (H'B2')

DATABYTE2 = Channel bit

Contents	Channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'10000000'	Channel 8

'Disable Channel Program' command received:

SID10-SID9 = 11 (lowest priority)

SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 5 databytes received

DATABYTE1 = COMMAND DISABLE PROGRAM (H'B1')

DATABYTE2 = channel

Contents	Channel
B'00000001'	Channel 1
B'00000010'	Channel 2
B'10000000'	Channel 8

DATABYTE3 = high byte of delay time

DATABYTE4 = mid byte of delay time

DATABYTE5 = low byte of delay time

Remark:

[DATABYTE3][DATABYTE4][DATABYTE5] contain a 24-bit time in seconds

The command will be skipped when the time parameter contains zero.

When the time parameter contains H'FFFFFF' then the channel program will be permanently disabled.

'Select Program' command received:SID10-SID9 = 11 (lowest priority) SID8...SID1 = Module address

RTR = 0

DLC3...DLC0 = 2 databytes received
DATABYTE1 = COMMAND_SELECT_PROGRAM (H'B3')
DATABYTE2 = Program mode

Contents	Selected programl
0	None
1	Summer
2	Winter
3	Holiday

Memory map:

Address	Contents	Address	Contents
H'0000'	Channel name character 1	H'0001'	Channel 1 name character 2
11 0000	Chainer hame character 1	11 0001	Chamier F hame character 2
H'000E'	Channel 1name character 15	H'000F'	Channel 1 name character 16
H'0010'	Channel 2 name character 1	H'0011'	Channel 2 name character 2
11 0010	Chamier 2 manie character 1	11 0011	Chamier 2 hame character 2
H'001E'	Channel 2name character 15	H'001F'	Channel 2 name character 16
H'0020'	Channel 3 name character 1	H'0021'	Channel 3 name character 2
11 0020	Chaimer 5 hame character 1	11 0021	Chamier 5 hame character 2
H'002E'	Channel 3name character 15	H'002F'	Channel 3 name character 16
H'0030'	Channel 4 name character 1	H'0031'	Channel 4 name character 2
H'003E'	Channel 4name character 15	H'003F'	Channel 4 name character 16
H'0040'	Channel 5 name character 1	H'0041'	Channel 5 name character 2
H'004E'	Channel 5name character 15	H'004F'	Channel 5 name character 16
H'0050'	Channel 6 name character 1	H'0051'	Channel 6 name character 2
H'005E'	Channel 6name character 15	H'005F'	Channel 6 name character 16
H'0060'	Channel 7 name character 1	H'0061'	Channel 7 name character 2
H'006E'	Channel 7name character 15	H'006F'	Channel 7 name character 16
H'0070'	Channel 8 name character 1	H'0071'	Channel 8 name character 2
H'007E'	Channel 8name character 15	H'007F'	Channel 8 name character 16
H'0080'	Channel 1 reaction time	H'0081'	Channel 2 reaction time
H'0086'	Channel 7 reaction time	H'0087'	Channel 8 reaction time
H'0088'	Channels inverted/non inverted	H'0089'	Led backlight on/off
H'008A'	Led backlight intensity	H'008C'	Led feedback on/off
H'008C'	Enable/disable slow blinking led feedback	H'008D'	Enable/disable fast blinking led feedback
H'008E'	Enable/disable very fast blinking led feedback	H'008F'	Led intensity (Build 1204 or higher)
H'0090'	Program selection (none/summer/winter/holiday)	H'0091'	Channel 81 prog disable/enable flags
H'0092'	Channel 81 locked/unlocked flags	H'0093'	Alarm clock configuration
H'0094'	Wake up 1 hour (023)	H'0095'	Wake up 1 minutes (059)
H'0096'	Go to bed 1 hour (023)	H'0097'	Go to bed 1 minutes (059)
H'0098'	Wake up 2 hour (023)	H'0099'	Wake up 2 minutes (059)
H'009A'	Go to bed 2 hour (023)	H'009B'	Go to bed 2 minutes (059)
H'009C'	Channel 1 start function	H'009D'	Channel 1 end function
H'00AA'	Channel 8 start function	H'00AB'	Channel 8 end function
H'00AC'	Multi function channels 81 auto reset enable	H'00AD'	Dual function channels 81 enable
H'00AE'	Dual function long pressed time	H'00AF'	Long pressed delay (Build 1204 or higher)
H'00B0'	Sunrise hour at 21 December (023)	H'00B1'	Sunrise minutes at 21 December (059)
H'00B2'	Sunrise 21 January – sunrise 5 January (-128'127')	H'00B3'	Sunrise 5 February – sunrise 21 January (-128'127')
H'00B4'	Sunrise 21 February – sunrise 5 February (-128'127')	H'00B5'	Sunrise 5 March – sunrise 21 February (-128'127')
H'00B6'	Sunrise 21 March – sunrise 5 March (-128'127')	H'00B7'	Sunrise 5 April – sunrise 21 March (-128'127')
H'00B8'	Sunrise 21 April – sunrise 5 April (-128'127')	H'00B9'	Sunrise 5 May – sunrise 21 April (-128'127')
H'00BA'	Sunrise 21 May – sunrise 5 May (-128'127')	H'00BB'	Sunrise 5 June – sunrise 21 May (-128'127')
H'00BC'	Sunrise 21 June – sunrise 5 June (-128'127')	H'00BD'	Sunrise 5 July – sunrise 21 June (-128'127')
H'00BE'	Sunrise 21 July – sunrise 5 July (-128'127')	H'00BF'	Sunrise 5 August – sunrise 21 July (-128'127')
H'00C0'	Sunrise 21 August – sunrise 5 August (-128'127')	H'00C1'	Sunrise 5 September – sunrise 21 August (-128'127')
H'00C2'	Sunrise 21 September – sunrise 5 September (-128127')	H'00C3'	Sunrise 5 October – sunrise 21 September (-128'127')
H'00C4'	Sunrise 21 October – sunrise 5 October (-128'127')	H'00C5'	Sunrise 5 November – sunrise 21 October (-128'127')
H'00C6'	Sunrise 21 November – sunrise 5 November (-128'127')	H'00C7'	Sunrise 5 December – sunrise 21 November (-128'127')
H'00C8'	Sunrise 21 December – sunrise 5 December (-128'127')	H'00C9'	Sunrise 5 January – sunrise 21 December (-128'127')

Address	Contents	Address	Contents
H'00CA'	Sunset hour at 21 December (023)	H'00CB'	Sunset minutes at 21 December (059)
H'00CC'	Sunset 21 January – sunrise 5 January (-128'127')	H'00CD'	Sunset 5 February – sunrise 21 January (-128'127')
H'00CE'	Sunset 21 February – sunrise 5 February (-128'127')	H'00CF'	Sunset 5 March – sunrise 21 February (-128'127')
H'00D0'	Sunset 21 March – sunrise 5 March (-128'127')	H'00D1'	Sunset 5 April – sunrise 21 March (-128'127')
H'00D2'	Sunset 21 April – sunrise 5 April (-128'127')	H'00D3'	Sunset 5 May – sunrise 21 April (-128'127')
H'00D4'	Sunset 21 May – sunrise 5 May (-128'127')	H'00D5'	Sunset 5 June – sunrise 21 May (-128'127')
H'00D6'	Sunset 21 June – sunrise 5 June (-128'127')	H'00D7'	Sunset 5 July – sunrise 21 June (-128'127')
H'00D8'	Sunset 21 July – sunrise 5 July (-128'127')	H'00D9'	Sunset 5 August – sunrise 21 July (-128'127')
H'00DA'	Sunset 21 August – sunrise 5 August (-128'127')	H'00DA'	Sunset 5 September – sunrise 21 August (-128'127')
H'00DC'	Sunset 21 September – sunrise 5 September (-128'127')	H'00DC'	Sunset 5 October – sunrise 21 September (-128'127')
H'00DE'	Sunset 21 October – sunrise 5 October (-128'127')	H'00DF'	Sunset 5 November – sunrise 21 October (-128'127')
H'00E0'	Sunset 21 November – sunrise 5 November (-128'127')	H'00E1'	Sunset 5 December – sunrise 21 November (-128'127')
H'00E2'	Sunset 21 December – sunrise 5 December (-128'127')	H'00E3'	Sunset 5 January – sunrise 21 December (-128'127')
H'00E4'	Not used	H'00E5'	Not used
H'00F8'	Not used	H'00F9'	Current day (131) (Build 1204 or higher)
H'00FA'	Current month (112) (Build 1204 or higher)	H'00FB'	Current year high byte (Build 1204 or higher)
H'00FC'	Current year low byte (Build 1204 or higher)	H'00FD'	Module Address
H'00FE'	Serial number high	H'00FF'	Serial number low

Remark:

Unused locations contain H'FF'

Do not overwrite the following address location:

H'0090' program selection H'0091' channel program enable/disable H'0092' channel locked/unlocked

H'00F9' current day of month
H'00FA' current month
H'00FB' & H'00FC' curent year
H'00FD' module address
H'00FE' & H'00FF' module serial number

Valid reaction times

Contents	Reaction time
H'05'	0.065s
H'4C'	1s
Н'99'	2s
H'E0'	3s
H'FF'	Channel disabled

Valid long pressed delay (Build 1204 or higher)

Contents	Reaction time
H'40'	0.8s
H'80'	1.6s
H'FF'	Default 0.8s

Channels inverted

Contents	Led feedback
B'xxxxxxx0'	Channel 1 inverted
B'xxxxxxx1'	Channel 1 not inverted
B'0xxxxxxx'	Channel 8 inverted
B'1xxxxxxx'	Channel 8 non inverted

Led Backlight on/off

Contents	Led backlight
B'xxxxxxx0'	Channel 1 off
B'xxxxxxx1'	Channel 1 on
B'0xxxxxxx'	Channel 8 off
B'1xxxxxxx'	Channel 8 on

Led backlight intensity

Contents	Led backlight intensity
H'01'	Minimum
H'FF'	Maximum

Led feedback on/off

Contents	Led feedback
B'xxxxxxx0'	Channel 1 off
B'xxxxxxx1'	Channel 1 on
B'0xxxxxxx'	Channel 8 off
B'1xxxxxxx'	Channel 8 on

Led intensity (Build 1204 or higher)

Contents	Led intensity
H'01'	Minimum
H'40'	Maximum

Slow blinking Led feedback on/off

Contents	Slow blinking Led feedback
B'xxxxxxx0'	Channel 1 off
B'xxxxxxx1'	Channel 1 on
B'0xxxxxxx'	Channel 8 off
B'1xxxxxxx'	Channel 8 on

Fast blinking Led feedback on/off

Contents	Fast blinking Led feedback
B'xxxxxxx0'	Channel 1 off
B'xxxxxxx1'	Channel 1 on
B'0xxxxxxx'	Channel 8 off
B'1xxxxxxx'	Channel 8 on

Very fast blinking Led feedback on/off

Contents	Very Fast blinking Led feedback
B'xxxxxxx0'	Channel 1 off
B'xxxxxxx1'	Channel 1 on
B'0xxxxxxx'	Channel 8 off
B'1xxxxxxx'	Channel 8 on

Program selection

og. um serection		
Contents	Selected program	
0	None	
1	Summer	
2	Winter	
3	Holiday	

Channel program disabled

tunitet p. 68. unt uisuoteu			
Contents	Channel program enabled/disabled		
B'xxxxxxx0'	Channel 1 programs enabled		
B'xxxxxxx1'	Channel 1 programs disabled		
B'0xxxxxxx'	Channel 8 programs enabled		
B'1xxxxxxx'	Channel 8 programs disabled		

Channel locked

Contents	Channel locked/unlocked	
B'xxxxxxx0'	Channel 1 unlocked	
B'xxxxxxx1'	Channel 1 locked	
B'0xxxxxxx'	Channel 8 unlocked	
B'1xxxxxxx'	Channel 8 locked	

Alarm clock configuration

Contents	Channel locked/unlocked
B'xxxxxxx0'	Alarm 1 disabled
B'xxxxxxx1'	Alarm 1 enabled
B'0xxxxx0x'	Local alarm 1
B'1xxxxx1x'	Global alarm 1
B'xxxxx0xx'	Alarm 2 disabled
B'xxxxx1xx'	Alarm 2 enabled
B'xxxx0xxx'	Local alarm 2
B'xxxx1xxx'	Global alarm 2
B'xxx0xxxx'	Sunrise disabled
B'xxx1xxxx'	Sunrise enabled
B'xx0xxxxx'	Sunset disabled
B'xx1xxxxx'	Sunset enabled
B'x0xxxxxx'	Summer time disabled
B'x1xxxxxx'	Summer time enabled

Channel x start/end function

Contents	Function
B'00000001'	Channel 1
B'00000010'	Channel 2
B'01000000'	Channel 7
B'10000000'	Channel 8

Remark:

For a normal one function button, the start and end function channel are the same.

For a multi function button, the start function channel must be less than the end function. At every press the next channel wil be send. When the end function channel is reached, the start channel will be send again at the next press.

For a dual function button, the start function channel will be send at a short press or the end function will be send at a long press.

Multi function auto reset

Julian Julian Company			
Contents	Multi function auto reset		
B'xxxxxxx0'	Channel 1 auto reset disabled		
B'xxxxxxx1'	Channel 1 auto reset enabled		
B'0xxxxxxx'	Channel 8 auto reset disabled		
B'1xxxxxxx'	Channel 8 auto reset enabled		

Remark: When auto reset is enabled, the start function will be loaded again after 3 seconds inactivity of the channel.

Dual function enable

Contents	Dual function
B'xxxxxxx0'	Channel 1 dual function disabled
B'xxxxxxx1'	Channel 1 dual function enabled
B'0xxxxxxx'	Channel 8 dual function disabled
B'1xxxxxxx'	Channel 8 dual function enabled

Remark:

For a dual function button, the start function channel will be send at a short press or the end function will be send at a long press.

The dual function overwrites the multi function mode.

Valid dual function long pressed times

The same of the sa		
Contents	Long pressed time	
H'4C'	1s	
H'99'	2s	
H'E0'	3s	

Address	Contents	Address	Contents
H'0100'	Linked Push button 1 module address	H'0101'	Linked Push button 1 bit number
H'0102'	Linked Push button 1 action	H'0103'	Linked Push button 1 time parameter
H'0104'	Linked Push button 1 channel parameter	H'0105'	Linked Push button 2 module address
H'0106'	Linked Push button 2 bit number	H'0107'	Linked Push button 2 action
H'0108'	H'0108' Linked Push button 2 time parameter		Linked Push button 2 channel parameter
H'010A'		H'010B'	
		H'01F5'	Linked Push button 50 module address
H'01F6'	Linked Push button 50 bit number	H'01F7'	Linked Push button 50 action
H'01F8'	Linked Push button 50 time parameter	H'01F9'	Linked Push button 50 channel parameter
H'01FA' Linked Push button 51 module address		H'01FB'	Linked Push button 51 bit number
H'01FC'	Linked Push button 51 action	H'01FD'	Linked Push button 51 time parameter
H'01FE'	Linked Push button 51 channel parameter	H'01FF'	Not used

Remark: Unused locations contain H'FF'

Action

Action	Action	Time	Bit number
number		parameter	
0	Switch status led indication	-	Channel bit
1	Lock channel at closed switch	-	Channel bit
2	Lock channel at opened switch	-	Channel bit
3	Lock channel	Timeout	Channel bit
4	Lock/unlock channel	Timeout	Channel bit
5	Unlock channel	-	Channel bit
6	Disable channel program at closed switch	-	Channel bit
7	Disable channel program at opened switch	-	Channel bit
8	Disable channel program channel	Timeout	Channel bit
9	Disable/enable channel program	Timeout	Channel bit
10	Enable channel program	-	Channel bit
11	Select no programs	-	-
12	Select summer programs	-	-
13	Select winter programs	-	-
14	Select holiday programs	-	-
15	Enable Alarm/Sunrise/Sunset at closed switch	-	Alarm/sunrise/sunset bit
16	Enable Alarm/Sunrise/Sunset at open switch	-	Alarm/sunrise/sunset bit
17	Disable Alarm/Sunrise/Sunset at closed switch	-	Alarm/sunrise/sunset bit
18	Disable Alarm/Sunrise/Sunset at open switch	-	Alarm/sunrise/sunset bit
19	Enable Alarm/Sunrise/Sunset	-	Alarm/sunrise/sunset bit
20	Enable/Disable Alarm/Sunrise/Sunset	-	Alarm/sunrise/sunset bit
21	Disable Alarm/Sunrise/Sunset	-	Alarm/sunrise/sunset bit

Bit Number

Contents	Bit number
B'00000001'	Channel 1 or Alarm1
B'00000010'	Channel 2
B'00000100'	Channel 3 or Alarm2
B'00001000'	Channel 4
B'00010000'	Channel 5 or Sunrise
B'00100000'	Channel 6 or Sunset
B'01000000'	Channel 7
B'10000000'	Channel 8

Time parameter

Time parameter Timeout 0 0s (No timer) 1 1s 2 2s 119 120 2min 121 2min15s 131 4min45s 3min 132 5min 133 5min30s 29min30s 182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min 228 5h	ime parameter	
1 1s 2 2s 1min59s 120 2min 121 2min15s 131 4min45s 32 5min 5min 133 5min30s 181 29min30s 30min 183 31min 211 212 1h 213 1h15min 227 4h45min		
2 2s 119 1min59s 120 2min 121 2min15s 131 4min45s 132 5min 133 5min30s 181 29min30s 182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min		
119 1min59s 120 2min 121 2min15s 131 4min45s 132 5min 133 5min30s 181 29min30s 182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min		
119 1min59s 120 2min 121 2min15s 131 4min45s 132 5min 133 5min30s 181 29min30s 182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min	2	
120 2min 121 2min15s 4min45s 132 5min 133 5min30s 181 29min30s 182 30min 183 31min 211 212 1h 213 1h15min 227 4h45min		
121 2min15s 131 4min45s 132 5min 133 5min30s 181 29min30s 182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min		
131		
131 4min45s 132 5min 133 5min30s 29min30s 182 30min 183 31min 211 212 1h 213 1h15min 227 4h45min	121	
132 5min 133 5min30s 181 29min30s 182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min		
133 5min30s 181 29min30s 182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min		
181		
182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min	133	
182 30min 183 31min 211 59min 212 1h 213 1h15min 227 4h45min		
183 31min 211 59min 212 1h 213 1h15min 227 4h45min		
211 59min 212 1h 213 1h15min 227 4h45min		
211 59min 212 1h 213 1h15min 227 4h45min	183	
212 1h 213 1h15min 227 4h45min		
213 1h15min 227 4h45min		
 227 4h45min	212	
227 4h45min	213	
	•••	
228 5h	227	
	228	
229 5h30min	229	
	•••	
237 9h30min		
238 10h		
239 11h	239	
	•••	
251 23h		
252 1d		
253 2d		
254 3d		
255 infinite	255	

Address	Contents	Address	Contents
H'0200'	Program step 1 byte1	H'0201'	Program step 1 byte2
H'0202'	Program step 1 byte3	H'0203'	Program step 1 byte4
H'0204'	Program step 1 byte5	H'0205'	Program step 1 byte6
H'03F8'	Program step 85 byte1	H'03F9'	Program step 85 byte2
H'03FA'	Program step 85 byte3	H'03FB'	Program step 85 byte4
H'03FC'	Program step 85 byte5	H'03FD'	Program step 85 byte6
H'03FE'	Not used	H'03FF'	Not used

Contents program byte1	Description
B'000xxxxx'	Disable program step
B'001xxxxx'	Absolute time
B'010xxxxx'	Wake up time 1 + relative time
B'011xxxxx'	Go to bed time 1 + relative time
B'100xxxxx'	Wake up time 2 + relative time
B'101xxxxx'	Go to bed time 2 + relative time
B'110xxxxx'	Sunrise + relative time
B'111xxxxx'	Sunset + relative time
B'xxx01111'	Rel. time = 3h45min
•••	
B'xxx00001'	Rel. time = 15min
B'xxx00000'	Rel. time = 0
B'xxx11111'	Rel. time = -15min
•••	
B'xxx10000'	Rel. time = -4h

Remark: Wake up, Go to bed, sunrise & sunset time are only allowed for weekly programs

Contents program byte2	Description
B'xxxx0000'	Weekly program
B'xxxx0001'	January
B'xxxx0010'	February
B'xxxx0011'	March
B'xxxx0100'	April
B'xxxx0101'	May
B'xxxx0110'	June
B'xxxx0111'	July
B'xxxx1000'	August
B'xxxx1001'	September
B'xxxx1010'	October
B'xxxx1011'	November
B'xxxx1100'	December
B'xxxx1101'	Monthly program
B'xxxx1110'	Monthly program
B'xxxx1111'	Monthly program

Contents program byte3	Description
B'xxx00000'	0h
B'xxx00001'	1h
B'xxx10111'	23h
B'xx1xxxxx'	Summer program
B'x1xxxxxx'	Winter program
B'1xxxxxxx'	Holiday program

Contents program byte4	Description
B'xx000000'	0min
B'xx000001'	1min
B'xx111011'	59min

Contents program byte4	Contents program byte2	Description
B'00xxxxxx'	B'0000xxxx'	Never
B'00xxxxxx'	B'0001xxxx'	Day 1 of the month
B'00xxxxxx'	B'0010xxxx'	Day 2of the month
B'01xxxxxx'	B'1111xxxx'	Day 31of the month
B'10xxxxxx'	B'0000xxxx'	Never
B'10xxxxxx'	B'0001xxxx'	Every Monday
B'10xxxxxx'	B'0010xxxx'	Every Tuesday
	•••	
B'10xxxxxx'	B'0111xxxx'	Every Sunday
B'10xxxxxx'	B'1000xxxx'	Every weekend (sa & su)
B'10xxxxxx'	B'1001xxxx'	Every working day (mofr)
B'10xxxxxx'	B'1010xxxx'	Every day except Sunday
B'10xxxxxx'	B'1011xxxx'	Every day
B'10xxxxxx'	B'1100xxxx'	Never
B'11xxxxxx'	B'1111xxxx'	Never

Contents program byte5	Action	
0	0s25 Pulse	
1	1s Pulse	
2	2s Pulse	
119	1min59s Pulse	
120	2min Pulse	
121	2min15s Pulse	
131	4min45s Pulse	
132	5min Pulse	
133	5min30s Pulse	
181	29min30s Pulse	
182	30min Pulse	
183	31min Pulse	
211	59min Pulse	
212	1h Pulse	
213	1h15min Pulse	
227	4h45min Pulse	
228	5h Pulse	
229	5h30min Pulse	
237	9h30min Pulse	
238	10h Pulse	
239	11h Pulse	
246	18h Pulse	
247	Press	
248	Long Press	
249	Release	
250	Lock	
251	Unlock	
252	No action	
255	No action	

Contents program byte6	Channel
B'00000001'	Channel 1
B'0000010'	Channel 2
B'00000100'	Channel 3
B'00001000'	Channel 4
B'00010000'	Channel 5
B'00100000'	Channel 6
B'01000000'	Channel 7
B'10000000'	Channel 8